

DAY-4:

Tasks

1.

Connect a USB webcam to your computer, install any required drivers, and verify that the webcam works by opening the default camera app and capturing a photo.

Steps to follow:

1. Connect the USB webcam to an available USB port on the computer.
2. Wait for Windows to detect the webcam automatically.
3. Open Device Manager and check under Cameras to confirm that the webcam was detected.
4. Windows automatically installs the required driver. If needed, the manufacturer's driver can be installed manually.
5. Opened the Camera app from the Windows Start menu.
6. Check the live video preview to make sure the webcam was working.
7. Capture a test photo using the Camera app.
8. Verify that the photo was saved successfully.

Expected Result:

The USB webcam was successfully connected, detected, and tested using the default Camera application.

2.

Set up a local printer (USB or network), install the correct driver, and print a test page to confirm successful installation.

Steps followed:

1. Connected the printer to the computer using a USB cable.

2. Switched on the printer and checked that it had paper and sufficient ink/toner.
3. Opened Settings -> Devices-> Printers & scanners.
4. Clicked Add a printer or scanner.
5. Waited for Windows to detect the connected printer.
6. Selected the printer from the list.
7. Windows installed the required printer driver automatically. If required, the manufacturer's driver was installed manually.
8. Opened the printer settings and selected Manage -> Print a test page.
9. Checked the printed page to confirm that the printer was working correctly.

Result:

The printer was successfully connected and installed, and a test page was printed successfully.

3.

Simulate a connectivity issue by unplugging the printer's USB cable, then use Windows Device Manager to identify and resolve the 'printer not detected' problem.

Hint: Check for error icons and use the 'Scan for hardware changes' option after reconnecting.

Steps followed:

1. Unplugged the printer's USB cable from the computer.
2. Opened Device Manager by right-clicking the Start button and selecting Device Manager.
3. Checked Printers, Print queues, and Universal Serial Bus controllers for the printer.
4. Looked for a yellow error icon, which could indicate a driver or hardware problem.

5. Reconnected the printer's USB cable firmly.
6. Turned on the printer and waited for Windows to detect it.
7. In Device Manager, clicked Action -> Scan for hardware changes.
8. Windows searched for newly connected hardware.
9. Checked whether the printer appeared again in Device Manager.
10. If necessary, right-clicked the printer and selected Update driver.
11. Opened Settings -> Devices -> Printers & scanners and confirmed that the printer was available.
12. Printed a test page to verify the connection.

Result:

After reconnecting the USB cable and selecting Scan for hardware changes, Windows detected the printer again and the printer was ready to use.

4.

A user reports that their webcam video is not displaying in Zoom, but it works in the default camera app. Troubleshoot and resolve the issue so the webcam works in both applications.

Hint:
Check if another app is using the webcam or if Zoom permissions are enabled.

Problem:

The webcam works correctly in the Windows Camera app, but no video appears when using Zoom.

Troubleshooting Steps:

1. Close other applications using the webcam
Closed the Camera app, Microsoft Teams, Skype, or any other application that might be using the webcam.

2. Restart Zoom

Completely closed Zoom and opened it again.

3. Check Windows camera permissions

Went to Settings -> Privacy -> Camera and made sure:

- Allow access to the camera on this device was enabled.
- Allow apps to access your camera was enabled.
- Allow desktop apps to access your camera was enabled.

4. Check Zoom's camera settings

Opened Zoom -> Settings -> Video and checked the Camera option.

5. Select the correct webcam

Selected the external USB webcam from the camera list instead of another available camera.

6. Test the video preview

Checked the preview window in Zoom to confirm that the webcam video was displayed.

7. Restart the computer

If the problem continued, restarted the computer and opened Zoom again.

8. Test in a Zoom meeting

Started a test meeting and verified that the webcam video was working.

Result:

The webcam was successfully made available in Zoom by closing applications that could be using the camera, enabling the required Windows permissions, and selecting the correct webcam in Zoom's video settings.