

# Mawlana Bhashani Science and Technology University Santosh, Tangail-1902.

## **Lab Report**

## **Department of Information and Communication Technology**

Report No: 02

**Report Name:** TCP Variants.

Course Title: Wireless and Mobile Communication Lab

Course Code: ICT-4202

Submitted By	Submitted To
Name: Siddiqul Islam ID: IT-16048 Session: 2015-16 4th Year 2nd Semester Dept. of Information & Communication Technology, MBSTU.	Nazrul Islam Assistant Professor Dept. of Information & Communication Technology, MBSTU.

### **Objective:**

We have to create a simple dumbbell topology, two client Node1 and Node2 on the left side of the dumbbell and server nodes Node3 and Node4 on the right side of the dumbbell. Let Node5 and Node6 form the bridge of the dumbbell. Use point to point links. Install a TCP socket instance on Node1 that will connect to Node3.install a UDP socket instance on Node2 that will connect to Node4.

#### **Source Code:**

#include <fstream></fstream>
#include "ns3/core-module.h"
#include "ns3/network-module.h"
#include "ns3/internet-module.h"
#include "ns3/point-to-point-module.h"
#include "ns3/applications-module.h"
using namespace ns3;
NS_LOG_COMPONENT_DEFINE ("FifthScriptExample");
//
//
// node 0 node 1

```
// +-----+ +------+

// | ns-3 TCP | ns-3 TCP |

// +-----+

// | 10.1.1.1 | 10.1.1.2 |

// +-----+

// | point-to-point | | point-to-point |

// +-----+

// | 5 Mbps, 2 ms

//

//
```

// We want to look at changes in the ns-3 TCP congestion window. We need // to crank up a flow and hook the CongestionWindow attribute on the socket // of the sender. Normally one would use an on-off application to generate a // flow, but this has a couple of problems. First, the socket of the on-off // application is not created until Application Start time, so we wouldn't be // able to hook the socket (now) at configuration time. Second, even if we // could arrange a call after start time, the socket is not public so we // couldn't get at it.

```
//
// So, we can cook up a simple version of the on-off application that does what
// we want. On the plus side we don't need all of the complexity of the on-off
// application. On the minus side, we don't have a helper, so we have to get
// a little more involved in the details, but this is trivial.
//
// So first, we create a socket and do the trace connect on it; then we pass
// this socket into the constructor of our simple application which we then
// install in the source node.
//
//
class MyApp: public Application
{
public:
 MyApp ();
 virtual ~MyApp();
 void Setup (Ptr<Socket> socket, Address address, uint32_t packetSize, uint32_t nPackets,
DataRate dataRate);
```

```
private:
 virtual void StartApplication (void);
 virtual void StopApplication (void);
 void ScheduleTx (void);
 void SendPacket (void);
 Ptr<Socket>
               m_socket;
 Address
              m_peer;
 uint32_t
             m_packetSize;
 uint32_t
             m_nPackets;
 DataRate
               m_dataRate;
 EventId
             m_sendEvent;
            m_running;
 bool
 uint32_t
             m_packetsSent;
};
MyApp::MyApp ()
 : m_socket (0),
```

```
m_peer (),
  m_packetSize (0),
  m_nPackets (0),
  m_dataRate (0),
  m_sendEvent (),
  m_running (false),
  m_packetsSent (0)
{
}
MyApp::~MyApp()
{
m_socket = 0;
}
void
MyApp::Setup (Ptr<Socket> socket, Address address, uint32_t packetSize, uint32_t nPackets,
DataRate dataRate)
{
 m_socket = socket;
 m_peer = address;
```

```
m_packetSize = packetSize;
 m_nPackets = nPackets;
 m_dataRate = dataRate;
}
void
MyApp::StartApplication (void)
{
 m_running = true;
 m_packetsSent = 0;
 m_socket->Bind ();
 m_socket->Connect (m_peer);
 SendPacket ();
}
void
MyApp::StopApplication (void)
{
 m_running = false;
```

```
if (m_sendEvent.IsRunning ())
  {
   Simulator::Cancel (m_sendEvent);
  }
 if (m_socket)
  {
   m_socket->Close ();
  }
}
void
MyApp::SendPacket (void)
{
 Ptr<Packet> packet = Create<Packet> (m_packetSize);
 m_socket->Send (packet);
 if (++m_packetsSent < m_nPackets)</pre>
  {
   ScheduleTx ();
```

```
}
}
void
MyApp::ScheduleTx (void)
{
 if (m_running)
  {
   Time tNext (Seconds (m_packetSize * 8 / static_cast<double> (m_dataRate.GetBitRate ())));
   m_sendEvent = Simulator::Schedule (tNext, &MyApp::SendPacket, this);
  }
}
static void
CwndChange (uint32_t oldCwnd, uint32_t newCwnd)
{
 NS_LOG_UNCOND (Simulator::Now ().GetSeconds () << "\t" << newCwnd);
}
static void
```

```
RxDrop (Ptr<const Packet> p)
{
 NS_LOG_UNCOND ("RxDrop at " << Simulator::Now ().GetSeconds ());
}
int
main (int argc, char *argv[])
{
 CommandLine cmd;
 cmd.Parse (argc, argv);
 NodeContainer nodes;
 nodes.Create (2);
 PointToPointHelper pointToPoint;
 pointToPoint.SetDeviceAttribute ("DataRate", StringValue ("5Mbps"));
 pointToPoint.SetChannelAttribute ("Delay", StringValue ("2ms"));
 NetDeviceContainer devices;
 devices = pointToPoint.Install (nodes);
```

```
Ptr<RateErrorModel> em = CreateObject<RateErrorModel> ();
 em->SetAttribute ("ErrorRate", DoubleValue (0.00001));
 devices.Get (1)->SetAttribute ("ReceiveErrorModel", PointerValue (em));
 InternetStackHelper stack;
 stack.Install (nodes);
 Ipv4AddressHelper address;
 address.SetBase ("10.1.1.0", "255.255.255.252");
 lpv4InterfaceContainer interfaces = address.Assign (devices);
 uint16_t sinkPort = 8080;
 Address sinkAddress (InetSocketAddress (interfaces.GetAddress (1), sinkPort));
 PacketSinkHelper packetSinkHelper ("ns3::TcpSocketFactory", InetSocketAddress
(Ipv4Address::GetAny (), sinkPort));
 ApplicationContainer sinkApps = packetSinkHelper.Install (nodes.Get (1));
 sinkApps.Start (Seconds (0.));
 sinkApps.Stop (Seconds (20.));
```

```
Ptr<Socket> ns3TcpSocket = Socket::CreateSocket (nodes.Get (0), TcpSocketFactory::GetTypeId
());
 ns3TcpSocket->TraceConnectWithoutContext ("CongestionWindow", MakeCallback
(&CwndChange));
 Ptr<MyApp> app = CreateObject<MyApp> ();
 app->Setup (ns3TcpSocket, sinkAddress, 1040, 1000, DataRate ("1Mbps"));
 nodes.Get (0)->AddApplication (app);
 app->SetStartTime (Seconds (1.));
 app->SetStopTime (Seconds (20.));
 devices.Get (1)->TraceConnectWithoutContext ("PhyRxDrop", MakeCallback (&RxDrop));
 Simulator::Stop (Seconds (20));
 Simulator::Run ();
 Simulator::Destroy ();
 return 0;
}
```

#### **Output:**

```
siddiqul@siddiqul:~/Desktop/ns-allinone-3.29/ns-3.29$ clear
 siddiqul@siddiqul:~/Desktop/ns-allinone-3.29/ns-3.29$ ./waf --run scratch/fifth
siddiqul@siddiqul:~/Desktop/ns-allinone-3.29/ns-3.29$ ./waf --run scratch/fifth
Naf: Entering directory `/home/siddiqul/Desktop/ns-allinone-3.29/ns-3.29/build'
[2563/2616] Compiling scratch/fifth.cc
[2564/2616] Compiling scratch/queue-discs-benchmark.cc
[2565/2616] Compiling scratch/subdir/scratch-simulator-subdir.cc
[2574/2616] Linking build/scratch/subdir/subdir
[2575/2616] Linking build/scratch/fifth
[2576/2616] Linking build/scratch/queue-discs-benchmark
Waf: Leaving directory `/home/siddiqul/Desktop/ns-allinone-3.29/ns-3.29/build'
Build commands will be stored in build/compile_commands.json
'build' finished successfully (1m16.848s)
 1.00419 536
 1.0093 1072
 1.01528 1608
 1.02167 2144
 1.02999 2680
 1.03831 3216
 1.04663 3752
 1.05495 4288
 1.06327 4824
 1.07159 5360
 1.07991 5896
 1.08823 6432
 1.09655 6968
 1.10487 7504
 1.11319 8040
 1.12151 8576
 1.12983 9112
 RxDrop at 1.13696
 1.13815 9648
1.1548 1072
1.16476 1340
 1.17232 1554
 1.18064 1738
 1.18896 1903
```

```
2.45271 8333
2.46103 8367
2.46935 8401
2.47767 8435
2.48599 8469
2.49431 8502
2.50263 8535
2.51095 8568
2.51927 8601
2.52759 8634
RxDrop at 2.53382
2.53682 8667
RxDrop at 2.54304
2.55258 1072
2.57267 1340
2.57865 1554
2.58583 1738
2.59415 1903
2.60247 2053
RxDrop at 2.6087
2.6117 2192
2.62002 1072
2.63003 1340
2.63664 1554
2.64496 1738
2.65328 1903
2.6616 2053
2.66992 2192
2.67824 2323
2.68656 2446
2.69488 2563
2.7032 2675
2.71152 2782
2.71984 2885
2.72816 2984
2.73648 3080
2.7448 3173
2.75312 3263
```

```
9.01808 7733
9.0264 7770
9.03472 7806
9.04304 7842
9.05136 7878
9.05968 7914
9.068
      7950
9.07632 7986
9.08464 8021
9.09296 8056
9.10128 8091
9.1096 8126
9.11792 8161
9.12624 8196
9.13456 8231
9.14288 8265
9.1512 8299
9.15952 8333
9.16784 8367
9.17616 8401
9.18448 8435
9.1928 8469
9.20112 8502
9.20944 8535
9.21776 8568
9.22608 8601
9.2344 8634
9.24272 8667
9.25104 8700
9.25936 8733
9.26768 8765
9.276 8797
9.28432 8829
9.29264 8861
9.30096 8893
9.30928 8925
9.3176 8957
siddiqul@siddiqul:~/Desktop/ns-allinone-3.29/ns-3.29$
```

#### **Conclusion:**

Transmission Control Protocol (TCP) uses a network congestion-avoidance algorithm that includes various aspects of an additive increase/multiplicative decrease (AIMD) scheme, along with other schemes including **slow start** and **congestion window**, to achieve congestion avoidance. The **TCP** 

**congestion-avoidance algorithm** is the primary basis for congestion control in the Internet. Per the end-to-end principle congestion control is largely a function of internet hosts, not the network itself. There are several variations and versions of the algorithm implemented in protocol stacks of operating systems of computers that connect to the Internet.