

MINGW64:/c/Users/LENOVO/git-demo1

LENOVO@DESKTOP-S97V08Q MINGW64 ~

```
$ git --version
git version 2.54.0.windows.1
```

LENOVO@DESKTOP-S97V08Q MINGW64 ~

```
$ pwd
/c/Users/LENOVO
```

LENOVO@DESKTOP-S97V08Q MINGW64 ~

```
$ mkdir git-demo
mkdir: cannot create directory 'git-demo': File exists
```

LENOVO@DESKTOP-S97V08Q MINGW64 ~

```
$ mkdir git-demo1
```

LENOVO@DESKTOP-S97V08Q MINGW64 ~

```
$ cd git-demo1
```

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1

```
$ vim hello.py
```

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1

```
$ git config --global user.name "prem"
```

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1

```
$ git config --global user.email "prem.thaiyuri@gmail.com"
```

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1

```
$ git config --list
diff.astextplain.textconv=astextplain
filter.lfs.clean=git-lfs clean -- %f
filter.lfs.smudge=git-lfs smudge -- %f
filter.lfs.process=git-lfs filter-process
filter.lfs.required=true
http.sslbackend=schannel
core.autocrlf=true
core.fscache=true
core.symlinks=false
pull.rebase=false
credential.helper=manager
credential.https://dev.azure.com.usehttppath=true
init.defaultbranch=master
user.email=prem.thaiyuri@gmail.com
user.name=prem
```

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1

```
$
```

 MINGW64:/c/Users/LENOVO/git-demo1

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1

\$ git init

Initialized empty Git repository in C:/Users/LENOVO/git-demo1/.git/

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1 (master)

\$ ls -la

total 33

drwxr-xr-x 1 LENOVO 197609 0 Jun 23 17:36 ./

drwxr-xr-x 1 LENOVO 197609 0 Jun 23 17:32 ../

drwxr-xr-x 1 LENOVO 197609 0 Jun 23 17:36 .git/

-rw-r--r-- 1 LENOVO 197609 48 Jun 23 17:30 hello.py

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1 (master)

\$ git add hello.py

warning: in the working copy of 'hello.py', LF will be replaced by CRLF the next time Git touches it

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1 (master)

\$ git status

On branch master

No commits yet

Changes to be committed:

(use "git rm --cached <file>..." to unstage)

new file: hello.py

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1 (master)

\$ git commit -m "this is v1 commit"

[master (root-commit) 576feef] this is v1 commit

1 file changed, 1 insertion(+)

create mode 100644 hello.py

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1 (master)

\$ vim hello.py

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1 (master)

\$ git add hello.py

warning: in the working copy of 'hello.py', LF will be replaced by CRLF the next time Git touches it

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1 (master)

\$ git status

On branch master

Changes to be committed:

(use "git restore --staged <file>..." to unstage)

modified: hello.py

MINGW64:/c/Users/LENOVO/git-demo1

```
$ git status
On branch master
Changes to be committed:
  (use "git restore --staged <file>..." to unstage)
        modified:   hello.py
```

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1 (master)

```
$ git commit -m "this is v2 commit"
[master 40cc897] this is v2 commit
1 file changed, 1 insertion(+)
```

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1 (master)

```
$ cat hello.py
print("git is used for version control system")
print("version control is nothing but updating the code changes by using commits")
```

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1 (master)

```
$ git log --oneline
40cc897 (HEAD -> master) this is v2 commit
576feef this is v1 commit
```

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1 (master)

```
$ git checkout 576feef
Note: switching to '576feef'.
```

You are in 'detached HEAD' state. You can look around, make experimental changes and commit them, and you can discard any commits you make in this state without impacting any branches by switching back to a branch.

If you want to create a new branch to retain commits you create, you may do so (now or later) by using -c with the switch command. Example:

```
git switch -c <new-branch-name>
```

Or undo this operation with:

```
git switch -
```

Turn off this advice by setting config variable advice.detachedHead to false

HEAD is now at 576feef this is v1 commit

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1 ((576feef...))

```
$ cat hello.py
print("git is used for version control system")
```

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1 ((576feef...))

```
$ :
```

MINGW64:/c/Users/LENOVO/git-demo1

1 file changed, 1 insertion(+)

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1 (master)

\$ cat hello.py

print("git is used for version control system")

print("version control is nothing but updating the code changes by using commits")

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1 (master)

\$ git log --oneline

40cc897 (HEAD -> master) this is v2 commit

576feef this is v1 commit

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1 (master)

\$ git checkout 576feef

Note: switching to '576feef'.

You are in 'detached HEAD' state. You can look around, make experimental changes and commit them, and you can discard any commits you make in this state without impacting any branches by switching back to a branch.

If you want to create a new branch to retain commits you create, you may do so (now or later) by using -c with the switch command. Example:

```
git switch -c <new-branch-name>
```

Or undo this operation with:

```
git switch -
```

Turn off this advice by setting config variable advice.detachedHead to false

HEAD is now at 576feef this is v1 commit

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1 ((576feef...))

\$ cat hello.py

print("git is used for version control system")

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1 ((576feef...))

\$ git checkout 40cc897

Previous HEAD position was 576feef this is v1 commit

HEAD is now at 40cc897 this is v2 commit

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1 ((40cc897...))

\$ cat hello.py

print("git is used for version control system")

print("version control is nothing but updating the code changes by using commits")

LENOVO@DESKTOP-S97V08Q MINGW64 ~/git-demo1 ((40cc897...))

\$ |