7/4/24, 12:49 AM about:blank

SQL Cheat Sheet: CREATE TABLE, ALTER, DROP, TRUNCATE

Command	Syntax	Description	Example
CREATE TABLE	MySQL/DB2: CREATE TABLE table_name (col1 datatype optional keyword, col2 datatype optional keyword,col3 datatype optional keyword,, coln datatype optional keyword)	CREATE TABLE statement is to create the table. Each column in the table is specified with its name, data type and an optional keyword which could be PRIMARY KEY , NOT NULL , etc.,	MySQL/DB2: CREATE TABLE employee (employee_id char(2) PRIMARY KEY, first_name varchar(30) NOT NULL, mobile int);
	MySQL/DB2:		MySQL/DB2
ALTER TABLE - ADD COLUMN	Option 1. ALTER TABLE table_name ADD column_name_1 datatypeADD COLUMN column_name_n datatype;	ALTER TABLE statement is used to add the columns to a table.	Option 1. ALTER TABLE employee ADD income bigint;
	Option 2. ALTER TABLE table_name ADD COLUMN column_name_1 datatypeADD COLUMN column_name_n datatype;		Option 2. ALTER TABLE employee ADD COLUMN income bigint;
ALTER TABLE - ALTER COLUMN	MacCOL ALTER TARIE Ashle asses MODIFY	MySQL: ALTER TABLE MODIFY COLUMN MODIFY COLUMN clause is used with the ALTER	MacCOL ALTER TABLE AND ADDRESS COLUMN
	MySQL: ALTER TABLE table_name MODIFY COLUMN column_name_1 new_data_type;	TABLE statement to modify the data type of	MySQL: ALTER TABLE employee MODIFY COLUMN mobile SET DATA TYPE CHAR(20);
	DB2: ALTER TABLE table_name ALTER COLUMN column_name_1 SET DATA TYPE datatype;	Db2: ALTER TABLE ALTER COLUMN statement is used to modify the data type of columns.	DB2: ALTER TABLE employee ALTER COLUMN mobile SET DATA TYPE CHAR(20);
ALTER TABLE -	Massol /DD2, at TED TABLE to black and DD2	ALTER TABLE DROP COLUMN statement is used to	MySQL/DB2:
DROP COLUMN	MySQL/DB2: ALTER TABLE table_name DROP COLUMN column_name_1;	remove columns from a table.	ALTER TABLE employee DROP COLUMN mobile ;
ALTER TABLE -	$MySQL: \texttt{ALTER TABLE table_name CHANGE} \\ \texttt{COLUMN current_column_name new_column_name} \\ \texttt{datatype [optional keywords];} \\$	MySQL: ALTER TABLE CHANGE COLUMN CHANGE COLUMN clause is used to rename the columns in a table.	$MySQL: \mbox{ALTER TABLE employee CHANGE COLUMN} \\ \mbox{first_name name VARCHAR(255);}$
RENAME COLUMN	DB2: ALTER TABLE table_name RENAME COLUMN current_column_name TO new_column_name;	DB2: ALTER TABLE RENAME COLUMN statement is used to rename the columns in a table.	DB2: ALTER TABLE employee RENAME COLUMN first_name TO name;
TRUNCATE TABLE		MySQL: TRUNCATE TABLE statement is used to delete all of the rows in a table.	
	MySQL: TRUNCATE TABLE table_name;		MySQL: TRUNCATE TABLE employee;
	$DB2$: TRUNCATE TABLE table_name IMMEDIATE;	Db2: The IMMEDIATE specifies to process the statement immediately and that it cannot be undone.	DB2: TRUNCATE TABLE employee IMMEDIATE;
DROP TABLE	MySQL/DB2DROP TABLE table_name ;	anntains data by default the data will be deleted	MySQL/DB2:
			DROP TABLE employee ;

Author(s)

<u>Himanshu Birla</u> <u>Niveditha Pandith TS</u>



Changelog

DateVersionChanged byChange Description2023-05-041.1Benny LiFormatting changes made2021-07-271.0Himanshu Birla Initial Version

about:blank 1/1