Exp.no: 11b
DATE : 15/10/26

SIMULATE RIP USING CISCO PACKET TRACER.


AIM:


To simulate RIP (Routing Information Protocol) using Cisco Packet Tracer.

PROCEDURE:

1) Open Cisco Packet Tracer.
2) Create the RIP topology containing PC0, PC1, Router0, Router1, Router2.
3) Connect the routers using the required Ethernet / Serial links according to the lab topology.
4) Configure IP address on all router interfaces.
5) Configure the IP address & default gateways on PC0 and PC1
6) Verify basic connectivity using:
   ping <destination-IP>
7) Open the CLI of Router 0 & Enter:

```
enable
configure terminal
router rip
version 2
network 10.0.0.0
network 192.168.1.0
network 20.0.0.0
no auto summary
exit.
```


Router0
Physical
Config
CLI
Attributes
GLOBAL
Settings
Algorithm Settings
ROUTING
Static
RIP
SWITCHING
VLAN Database
INTERFACE
FastEthernet0/0
FastEthernet0/1
Serial0/1/0
Serial0/1/1
RIP Routing
Network
Add
Network Address
10.0.0.0
192.168.1.0
Remove
Equivalent IOS Commands
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/1/1
Router(config-if)#
Router(config-if)#
Router(config-if)#exit
Router(config)#router rip
Router(config-router)#network 10.0.0.0
Router(config-router)#network 192.168.1.0
Router(config-router)#no network 192.168.1.0
Router(config-router)#network 192.168.1.0
Router(config-router)#
Router2
GLOBAL
Settings
Algorithm Settings
ROUTING
Static
RIP
SWITCHING
VLAN Database
INTERFACE
FastEthernet0/0
FastEthernet0/1
Serial0/1/0
Serial0/1/1
FastEthernet1/0
RIP Routing
Network
Add
Network Address
20.0.0.0
192.168.1.0
Remove
Equivalent IOS Commands
%LINK-5-CHANGED: Interface Serial0/1/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/1, changed state to up
ip address 192.168.1.253 255.255.255.252
Router(config-if)#ip address 192.168.1.253 255.255.255.252
Router(config-if)#
Router(config-if)#exit
Router(config)#router rip
Router(config-router)#network 20.0.0.0
Router(config-router)#network 192.168.1.0
Router(config-router)#


Logical
Physical
x: 766, y: 291
2811
Router1
2811
Router0
2811
Router2
PC-PT
PC0
PC-PT
PC1

8) Configure RIP on Router 1 & Router 2 using its directly connected networks.

9) Verify the routing table:

Show ip route

10) Look for routes marked with : R

11) From PC0, use:

tracert <PC1-IP>

12) Disconnect the cable corresponding to the primary route.

13) Wait for RIP to update the routing information.

14) Run tracert again.

15) Observe the RIP automatically selects another available route.

RESULT:

Thus the RIP was successfully configured in CISCO Packet Tracer.