
PRACTICAL 2


2520090160 - BUJANAGRI SNIGDHA

Linux Virtual Machine Creation

Step-wise procedure:

Click on launch instance.
Name it as – My_Linux_Virtual_Machine
Choose application – Amazon Linux







Create a new key pair

Name the key as – Key1

Keep the default selected options as it is same





Come back to instance page and select the instance to connect




Choose EC2 Instance Support and IPv4 and connect

Linux Virtual Machine is created





Stop the instance after done or terminate it




Windows Virtual Machine Creation


Step-wise procedure:


Click on launch instance.


Name it as – My_windows _VM


Choose application – Windows




EC2 > Instances > Launch an instance
Key pair (login) Info
You can use a key pair to securely connect to your instance. Ensure that you have access to the selected key pair before you launch the instance.
Key pair name - required
windowskey
Create new key pair
For Windows instances, you use a key pair to decrypt the administrator password. You then use the decrypted password to connect to your instance.
Network settings Info
Edit
Network Info
vpc-0ff9bd74126f08743
Subnet Info
No preference (Default subnet in any availability zone)
Auto-assign public IP Info
Enable
Firewall (security groups) Info
A security group is a set of firewall rules that control the traffic for your instance. Add rules to allow specific traffic to reach your instance.
Create security group
Select existing security group
We'll create a new security group called 'launch-wizard-2' with the following rules:
Allow RDP traffic from
Helps you connect to your instance
Allow HTTPS traffic from the internet
To set up an endpoint, for example when creating a web server
Allow HTTP traffic from the internet
To set up an endpoint, for example when creating a web server
Rules with source of 0.0.0.0/0 allow all IP addresses to access your instance. We recommend setting security group rules to allow access from
Summary
Number of instances Info
1
Software Image (AMI)
Microsoft Windows Server 2025 ...read more
ami-0b5f645abc199e666
Virtual server type (instance type)
t3.micro
Firewall (security group)
New security group
Storage (volumes)
1 volume(s) - 30 GiB
Cancel
Launch instance
Preview code


Search [Alt+S]
United States (N. Virginia)
Snigdha
EC2 > Instances > i-0095d5862ed984c28 > Connect to instance
Connect to Windows instance Info
Connect to an instance to test, troubleshoot, deploy code, update software etc. You can use browser based methods or an RDP client.
Instance info
Instance
i-0095d5862ed984c28 (My_windows_VM)
State: Running
Status: 3/3 checks passed
VPC
vpc-0ff9bd74126f08743
Subnet
subnet-042dc98d355b8c0eb
Security groups
sg-0dfd0c4afc5e2c304 (launch-wizard-2)
In web browser
RDP (Remote Desktop Protocol)
Choose how to connect
Maximum security IAM authentication
SSM Session Manager
Uses IAM-based authentication. Connect without SSH keys, bastion hosts, or opening any inbound ports.
Remote desktop SSM agent-based
Fleet Manager
Browser-based remote desktop session powered by Systems Manager. Supports copy-paste between your local machine and remote session.
Direct Troubleshoot
EC2 Serial Console
Access your instance's serial port for troubleshooting boot, network, and OS issues. Works without network connectivity. Requires account-level enablement.
SSM agent info
Ping status
-
Session Manager connection status
Not connected
SSM agent version
-
IAM role
-
Systems Manager default role not enabled (No SSM fallback)
DHMC is not enabled and IAM instance profile is not attached
To connect to an instance using Session Manager, you can either set up SSM permissions by default for all instances in your account using the default host management configuration (DHMC), or link an IAM role with required permissions to this instance. Learn more
DHMC setup
Modify IAM role
Cancel
Connect assist
Connect
CloudShell
Agent Toolkit for AWS
Feedback
Console Mobile App
© 2026, Amazon Web Services, Inc. or its affiliates.
Privacy
Terms
Cookie preferences


Connect to Windows instance Info
Connect to an instance to test, troubleshoot, deploy code, update software etc. You can use browser based methods or an RDP
Instance info
Instance
i-0095d5862ed984c28 (My_windows_VM)
State: Running
Status: 3/3 checks passed
VPC
vpc-0ff9bd74126f08743
In web browser
RDP (Remote Desktop Protocol)
How to connect
1. Open or install a remote desktop client
2. Download the RDP shortcut file
3. Open the RDP client and run the shortcut file
4. Retrieve password
5. Enter username and password
6. Connect
RDP shortcut file
Download
Public DNS
ec2-54-91-221-139.compute-1.amazonaws.com
If you've joined your instance to a directory, you can use your directory credentials to connect to your instance.
Remote Desktop Connection security warning
Caution: Unknown remote connection
This remote connection could harm the local or remote computer and may be used to steal passwords or files. We could not verify the publisher of this remote connection. Stop now unless you are certain you trust this connection. Contact your IT department if unsure. Learn more.
Publisher: Unknown publisher
Type: Remote Desktop Connection
Remote computer: ec2-54-91-221-139.compute-1.amazonaws.com
Allow the remote computer to access the following resources on my computer:
Smart cards or Windows Hello for Business
WebAuthn (passkeys and security keys)
Clipboard
Printers
Changes to these options apply only to this connection launch.
Connect
Cancel


ec2-54-91-221-139.compute-1.amazonaws.com
Recycle Bin
Microsoft Edge
EC2 Feedback
EC2 Microso...
My_windows_VM -...


Linux GUI Creation


Step-by-step procedure:


Launch an instance

Here I named as – Linux_GUI

Choose application as - Ubuntu






Network settings Info
VPC - required | Info
vpc-0ff9bd74126f08743 (default)
172.31.0.0/16
Subnet | Info
No preference
Create new subnet
Availability Zone | Info
No preference
Enable additional zones
Auto-assign public IP | Info
Enable
Firewall (security groups) | Info
A security group is a set of firewall rules that control the traffic for your instance. Add rules to allow specific traffic to reach your instance.
Create security group
Select existing security group
Security group name - required
launch-wizard-3
This security group will be added to all network interfaces. The name can't be edited after the security group is created. Max length is 255 characters. Valid characters: a-z, A-Z, 0-9, spaces, and ._-:/()#,@[]+=&;{}!$*
Description - required | Info
launch-wizard-3 created 2026-11-11T07:01:55.402Z
Inbound Security Group Rules
Security group rule 1 (TCP, 22, 106.77.165.101/32)
Remove
Type | Info
ssh
Protocol | Info
TCP
Port range | Info
22
Source type | Info
My IP
Name | Info
Add CIDR, prefix list or security group
Description - optional | Info
e.g. SSH for admin desktop
106.77.165.101/32
Security group rule 2 (TCP, 3389, 106.77.165.101/32)
Remove
Type | Info
rdp
Protocol | Info
TCP
Port range | Info
3389
Source type | Info
My IP
Name | Info
Add CIDR, prefix list or security group
Description - optional | Info
e.g. SSH for admin desktop
106.77.165.101/32
Add security group rule

Enabled

Metadata IPv6 endpoint | Info

Select

Metadata version | Info

V2 only (token required)

⚠ For V2 requests, you must include a session token in all instance metadata requests.
Applications or agents that use V1 for instance metadata access will break.

Metadata response hop limit | Info

2

Allow tags in metadata | Info


Select


User data – *optional* | Info

Upload a file with your user data or enter it in the field.

Choose file

```
#!/bin/bash
apt update -y
DEBIAN_FRONTEND=noninteractive apt install -y xfce4 xfce4-goodies xrdp
echo "xfce4-session" > /home/ubuntu/.xsession
chown ubuntu:ubuntu /home/ubuntu/.xsession
adduser xrdp ssl-cert
echo "ubuntu:ChangeThisPassword@123" | chpasswd
systemctl enable xrdp
systemctl restart xrdp
```








Storage Creation using S3

Step-by-step procedure:

In console search for S3 choose Bucket and create a bucket






Upload Info
Add the files and folders you want to upload to S3. To upload a file larger than 160GB, use the AWS CLI, AWS SDKs or Amazon S3 REST API. Learn more
Drag and drop files and folders you want to upload here, or choose Add files or Add folder.
Files and folders (5 total, 5.9 MB)
All files and folders in this table will be uploaded.
Remove
Add files
Add folder
Find by name
1
Name
Folder
Type
Size
Cat_November_2010-1a.jpg.webp - image/webp 280.3 KB
IPC_Chat_Application.pptx - application/vnd.openxmlformats-officedocument.pr... 77.0 KB
visionport.html - text/html 1.9 KB
PRACTICAL 2.docx - application/vnd.openxmlformats-officedocument.wo... 4.1 MB
PRACTICAL 1.pdf - application/pdf 1.4 MB
Destination Info
Destination
s3://sniggssmemory
Destination details
Bucket settings that impact new objects stored in the specified destination.
Permissions
Grant public access and access to other AWS accounts.