

28/9/26

- docker ps
- docker ps -a
- docker start democon
- docker ps
- docker stop democon
- docker ps
- docker rm democon
- docker ps -a

You cannot remove the container while running. Stop then remove. If needed, then force stop.

- docker start ad09079a1be4
- docker ps

- docker rm ad09079a1be4 → container name/id
- docker rm -f ad09079a1be4 → force remove when the container is running.
- docker ps -a

- docker run -d --name sjc-derops httpd
- ↓
no need of manual start
automatically starts
- daemon (background process)
- can give name for container.

- docker ps
- docker run --name sjc-derops httpd
- docker run --name sjc-derops-1 httpd

- docker ps
- docker ps -a
- docker start sjc-derops-1
- docker ps

- docker exec -it sjc-derops /bin/bash
- to open container ↓
to open interactive terminal
- exit
- terminal specifying path

Apache configuration: [static
open container, then
hastings]

- apt update

2) Move to root directory of Apache engine to configure (Not root user)

source code

- cd /etc
- ls -l
- cat index
- exit

→ [1] po

→ Need

↑ should use http

• IP co

• took

• http:

• doc

Task
Ap
por
co

should use http not https

source code.


- cd httpd
- ls - (httpd) → root dir & source code
- cat index.html default file
- exit

→ [port la multicontainer work aagathu] ^{only docker inside}

→ Need host IP.

↳ IP config [to get IP of local host] wireless LAN-IPV4

- took host IP
- http:// IP : 8082
- docker run -d --name test



Task

- Apache image
- Port: 82
- Container name: task
- Customized webpage.

Note: -d kudukala na, start kudukalam so ur la varadhui, nna in bg.

→ start agidum, check by docker ps.

- Copy local host IP & paste in browser with http:// IP 8082

[if port not free, create another container & launch with other free port]

docker run -d --name task -p 82:80 httpd

- docker ps
- docker exec -it task /bin/bash

ipconfig

container backup
 • docker ps
 • docker commit test snapimg:1.0
 ↑
 version/tag
 • docker images
 • docker run -d --name demo -p 8083:80 snapimg:1.0
 backup agum but load agathu. [container than backup edathu Image kadalhu.]
 • docker save -o sjcbakup.tar snapimg:1.0
 • docker load -i sjcbakup.tar

Docker image store pannam means,

- docker save snapimg:1.0 > demo backup.tar
 ↑
 file extension.
- ls

"tar la panna than recognize pannam when we want another time to open in Docker."

- docker rmi snapimg:1.0 → remove image

"container la image use panna, we can't remove it". we can force stop.

- docker load -i sjcbakup.tar
 ↑
 backup file name.

- docker images

→ Dockerfile - build the image.

↳ text document but should not give .txt as its filename.

↳ should not give extensions.

INSTRUCTION arguments } syntax

Dockerfile:

Docker ca
 the Instru
 test down
 user coul
 assemble

INSTRU

1) FRO

2) RU

3) EX

4) W

5) E

6)

1)


Dockerfile:

Docker can build images automatically by reading the instructions from a Dockerfile. A Dockerfile is a text document that contains all the commands a user could call on the command line to assemble an image.

INSTRUCTIONS:

- 1) FROM - create new build stage from a base image.
- 2) RUN - Execute build commands.
- 3) EXPOSE - Describe which ports or app is listening on.
- 4) WORKDIR - Change working directory.
- 5) ENV - Set environment variables.
- 6) CMD - Specify default commands.
↓
can override
- 7) ENTRYPOINT → cannot override but same as CMD.
↓
Specify default executable.

DOCKER Network:



default - bridge