

Recurring & Non Recurring Sounds


Part-2

Introduction

In this tutorial you will how to setup Recurring and Non Recurring Sounds for the AI agent.

Humanoid Ai Audio Player

The script is responsible for playback of different sounds and phrases in various situations. When Ai agent is wounded or dying or reloading weapons or engaging his enemy etc.



Fields	Info
AudioSourceComponent	Drag and drop audio source component which is the child of this Ai agent from the hierarchy into this field.
DyingAudioClips	Drag and drop one or more dying sound clips from the project into this field.
FireSoundAudioSourceComponent	Drag and drop audio source component which is the child of this Ai agent from the hierarchy into this field.
ReloadSoundAudioSourceComponent	Drag and drop audio source component which is the child of this Ai agent from the hierarchy into this field.
WeaponShotAudioClip	Drag and drop 'Fire sound clip' from the project window into this field.
WeaponReloadAudioClip	Drag and drop the Reload Sound clip from the project window into this field.
FootStepsAudioSourceComponent	Drag and drop audio source component which is the child of this Ai agent from the hierarchy into this field.
FootStepAudioClip	Drag and drop 'Footstep sound clip' from the project window into this field.
AudioSourceComponent (Replayable Voices)	Drag and drop the audio source component which is the child of this

	AI agent from the hierarchy into this field.
DefaultBehaviourAudioClips	Drag and drop default behavior audio clips from the project window into this field.
EngagingTheEnemyAudioClips	Drag and drop engaging the enemy audio clips from the project window into this field.
FollowerAudioClips	Drag and drop follower audio clips from the project window into this field.
LeaderAudioClips	Drag and drop leader audio clips from the project window into this field.
MinTimeBetweenRecurringAudioClips	Minimum time interval between recurring audio clips. Example: '1.0' seconds.
MaxTimeBetweenRecurringAudioClips	Maximum time interval between recurring audio clips. Example: '2.0' seconds.
MinRecurringAudioClipsDelayAfterInterruption	Minimum delay after interruption before recurring audio clips can play again. Example: '2.0' seconds.
MaxRecurringAudioClipsDelayAfterInterruption	Maximum delay after interruption before recurring audio clips can play again. Example: '4.0' seconds.
AudioSourceComponent (OneTime Voices)	Drag and drop the audio source component which is the child of this AI agent from the hierarchy into this field.
OnceReloadingAudioClips	

	Drag and drop reloading audio clips from the project window into this field.
OnceMeleeAudioClips	Drag and drop melee audio clips from the project window into this field.
OnceEmergencyAudioClips	Drag and drop emergency audio clips from the project window into this field.
OnceDeadBodyInvestigationAudioClips	Drag and drop dead body investigation audio clips from the project window into this field.
OnceHearingInvestigationAudioClips	Drag and drop hearing investigation audio clips from the project window into this field.
OnceWoundedAudioClips	Drag and drop wounded audio clips from the project window into this field.
OnceEnemyLostAudioClips	Drag and drop enemy lost audio clips from the project window into this field.
OnceTargetKilledAudioClips	Drag and drop target killed audio clips from the project window into this field.
OnceGrenadeAlertAudioClips	Drag and drop grenade alert audio clips from the project window into this field.
OnceThrowingGrenadeAudioClips	Drag and drop throwing grenade audio clips from the project window into this field.
OnceLeaderAtHaltPointAudioClips	

	Drag and drop leader at halt point audio clips from the project window into this field.
MinNonRecurringAudioClipsDelay	Minimum delay between non-recurring audio clips. Example: '1.0' seconds.
MaxNonRecurringAudioClipsDelay	Maximum delay between non-recurring audio clips. Example: '2.0' seconds.
RecurringSounds	Settings for recurring sound clips based on time intervals. Example: 'Default behavior sounds that play at random intervals while the AI is patrolling.'
NonRecurringSounds	Settings for non-recurring sound clips that play once under specific conditions. Example: 'Emergency state sound that plays once when the AI enters an emergency state.'
DyingSounds	Settings for dying sound clips that play when the AI agent dies.
WeaponSounds	Settings for weapon sound clips that play during firing and reloading actions.
DefaultFootStepSounds	Settings for footstep sound clips that play when the AI agent moves.