


Sound Investigation & Emergency Behaviour Part-6

Introduction

In this tutorial you will learn how AI agent overrides sound investigation when emergency state activate.


Alerting Sound Reaction

When the option 'Force Emergency State' is selected, if an AI agent is moving towards a sound coordinate and enters a trigger radius where the 'Alerting Sound Reaction' is set to 'Force Emergency State,' the AI agent will immediately enter the emergency state and stop moving towards the sound coordinate.



AI Hearing

This paragraph contains fields related to AI agent reactions to alerting sounds.



Fields	Info
SoundAlertProbability	This slider sets the probability of this AI agent to react to sound alerts.
MoveTowardsSoundCoordinate	If checked, then Ai agent will move towards the alerting coordinate. Otherwise, he will look in the direction of that sound for a specified amount of time.
RecieveFriendlySoundCoordinate	If checked, then AI agent will join his friendly in alerting sound investigation if that friendly affects this agent with his sound alert radius. That secondary sound alert radius communicates the sound alert to all agents that got within this radius (even in cases when those agents are having zero probability to move out

	towards initial alerting sound that they heard themselves).
ShareSoundCoordinatesComponent	Reference to the component responsible for sharing sound coordinates.
EnableSprintingTowardsSoundCoordinate	Enable/disable sprinting towards sound coordinates.
MinSprintDistance	Minimal remaining distance to initial sound alert coordinate for the switch from walking or running to sprinting towards it.
MaxSprintDistance	Maximal remaining distance to initial sound alert coordinate for the switch from walking or running to sprinting towards it.
MinRunDistance	Minimal remaining distance to initial sound alert coordinate for the switch from walking or sprinting to running towards it.
MaxRunDistance	Maximal remaining distance to initial sound alert coordinate for the switch from walking or sprinting to running towards it.
MinWalkDistance	Minimal remaining distance to initial sound alert coordinate for the switch from running or sprinting to walking towards it.
MaxWalkDistance	Maximal remaining distance to initial sound alert coordinate for the switch from running or sprinting to walking towards it.
MinNearStoppingDistance	Minimum remaining distance to stop near the initial sound alert coordinate and to consider it as reached.
MaxNearStoppingDistance	Maximum remaining distance to stop near the initial sound alert coordinate and to consider it as reached.

MinTimeAtSoundAlertPoint	Set the minimum time the AI agent waits at the initial sound alert coordinate before returning to idle state.
MaxTimeAtSoundAlertPoint	Set the maximum time the AI agent waits at the initial sound alert coordinate before returning to idle state.
MinTimeToLookAtSoundAlertPoint	Set the minimum time the Stationary AI agent or agent with zero probability of moving towards initial sound alert coordinate, will look in the direction of the initial sound alert coordinate before returning to idle state.
MaxTimeToLookAtSoundAlertPoint	Set the maximum time the Stationary AI agent or agent with zero probability of moving towards initial sound alert coordinate, will look in the direction of the initial sound alert coordinate before returning to idle state.