


Player Setup

Introduction

This video guides you through the initial steps for getting started with the Player in Unity. We'll be adding the Player in the city using editor windows, integrating necessary components and game objects. Furthermore, we'll be talking about some important scripts like First person controller, Player Manager, Crouch, Procedural bobbing and other scripts. Will also fine-tune values in those scripts and will also make sure to test the player setup.

Setup Player


Firstly, you have to go to the Tools < Mobile Action Kit < Player < Player < Create Player. This will automatically create the player for you and will reset its position and rotation. You can just position it to the city and push play in unity to test it.



Two Types of Player Running Option

You can choose either 'Run or Walk Switch' Or Hold Run. The difference between both is If you choose 'Hold Run' than you can hold the Run UI button to move the player in the forward direction with the set amount of speed specified in the First Person Controller script paragraph named as 'Speeds'. If you choose 'Run or Walk Switch' than you can switch between either Run or walk by clicking on the Run UI button this button by default have the 'Run Sprite' meaning if you click on it, The image will be changed to

'Walk Sprite' which allow the player to use the Joystick to navigate around the city with the run speed specified in the First Person Controller script paragraph named as 'Speeds'. If you click on the Run UI button again which now have the 'Walk Sprite' this will change the sprite to 'Run Sprite' and this will allow the player to use the joystick to navigate around the city with the walk speed specified in the First Person Controller script paragraph named as 'Speeds'.




The Player Manager script manages various player HUD Ui elements for interactions with game environment and Weapons.

Fields	Info
Switching Player Weapons Component	'SwitchingPlayerWeapons' GameObject with 'SwitchingPlayerWeapons' script component attached to it is to be placed into this field.
Fire Button	

	'FireButton' GameObject with 'Button' component attached to it is to be placed into this field.
Reload Button	'ReloadButton' GameObject with 'Button' component attached to it is to be placed into this field.
Aiming Button	'AimingButton' GameObject with 'Button' component attached to it is to be placed into this field.
Run Options	Choose one of the two available running activation options: • RunOrWalkSwitch: Alters movement joystick to always walk or always run depending on the state of the 'Run' button. • HoldToRun: The 'Run' button acts as a dedicated running button that needs to be kept pressed for the player to run.
Walking Sprite	Walking sprite from the project is to be placed into this field.
Running Sprite	Running sprite from the project is to be placed into this field.
Player Weapon Scripts	All 'ShootingPoint' GameObjects of all the weapons from the player's hierarchy are to be placed into this list.

Crouch

Crouch script Controls The Player Crouch Behaviour.



Fields	Info
Player Camera	Reference to the player's camera. Used for adjusting the camera's height when crouching or standing.
Sit Down Speed	Speed at which the player crouches down.
Stand Up Speed	Speed at which the player stands up.
Crouch Height	The height of the camera when crouching.
Stand Height	The height of the camera when standing.
Stand Capsule Collider	Collider used when the player is standing.
Crouch Capsule Collider	Collider used when the player is crouching.
Standing Sprite	Sprite to show when the crouch button is toggled to a standing position.
Crouching Sprite	Sprite to show when the crouch button is toggled to a crouching position.

First Person Controller

This Script Controls The Player Walk,Sprint,Jump and TouchPad Behaviour.

First Person Controller (Script)

?

Script

FirstPersonController

Script Info

This Script Controls The Player Walk,Sprint,Jump and TouchPad Behaviour

Player Camera

Player Camera (Camera)

Joystick Script

Joystick (Joy Stick)

Touchpad Look

X Sensitivity

0.06

Y Sensitivity

0.06

Clamp Vertical Rotation

☒

Minimum X

-90

Maximum X

90

Smooth

☒

Smooth Time

15

Lock Cursor

☐

Look Axis

X 0Y 0

Weapon Aimed Touch Pad Look Values

X Sensitivity

0.008

Y Sensitivity

0.008

Smooth

☒

Smooth Time

15

Speeds

Walking Speed

35

Crouching Speed

20

Aimed Walking Speed

18

Aimed Crouching Speed

10

Run Speed On Standing

70

Run Speed On Crouching

40

Player Fall Speed

10

Walk And Run Sounds

Stand Run Steps Sound Trigger

Stand Run FootSteps Sounds (Alerting Sound Activator)

Crouch Run Steps Sound Trigger

Crouch Run FootSteps Sounds (Alerting Sound Activator)

Aimed Stand Walk Steps Sound Trigger

Aimed Stand Walk FootSteps Sounds (Alerting Sound Activator)

Aimed Crouch Walk Steps Sound Trigger

Aimed Crouch Walk FootSteps Sounds (Alerting Sound Activator)

Stand Walk Steps Sound Trigger

Stand Walk FootSteps Sounds (Alerting Sound Activator)

Crouch Walk Steps Sound Trigger

Crouch Walk FootSteps Sounds (Alerting Sound Activator)

Walking Sounds

2

Element 0

Walk Step (Audio Source)

Element 1

Cloth Step (Audio Source)

Running Sounds

2

Element 0

Run Step (Audio Source)

Element 1

Cloth Step (Audio Source)

Time Between Stand Sprint Steps

0.4

Time Between Crouch Sprint Steps

0.8

Time Between Stand Walk Steps

0.6

Time Between Crouch Walk Steps

0.8

Time Between Aimed Stand Steps

1

Time Between Aimed Crouch Steps

1.2

Jump

Jump Button

Jump Button (Button)

Jump Button Activation Delay

0.3

Stand Jumping Meters

2

Stand Jumping Duration

0.4

Stand Falling Duration

0.4

Crouch Jumping Meters

1

Crouch Jumping Duration

0.2

Crouch Falling Duration

0.2

Jump Start Sound

Jump Start (Audio Source)

Jump Landing Sound


Jump Land (Audio Source)

Fields	Info
Player Camera	Reference to the player's camera. Controls the player's view during movement, sprinting, jumping, and aiming.
Joystick Script	Script for managing the player's joystick input for movement control.
TouchPad Look	Handles touchpad input for controlling the player's aim and camera movement.
Weapon Aimed TouchPad Look Values	Settings for touchpad sensitivity when aiming weapons.
Speeds	Contains the player's movement speeds for different states such as walking, running, crouching, and aiming.
Run Speed On Standing	Speed of the player while running in a standing position.
Run Speed On Crouching	Speed of the player while running in a crouched position.
Player Fall Speed	How fast the player falls when in air.
Walk and Run Sounds	Manages footstep sounds for walking, running, crouching, and aiming.
Stand Run Steps Sound Trigger	Sound trigger for footstep sounds when the player is running while standing.
Crouch Run Steps Sound Trigger	Sound trigger for footstep sounds when the player is running while crouching.
Time Between Stand Sprint Steps	The time interval between footstep sounds while sprinting in a standing position.
Time Between Crouch Sprint Steps	The time interval between footstep sounds while sprinting in a crouched position.
Jump	Handles jump settings, including jump height, duration, and associated sounds.

Jump Button	Reference to the button used to trigger the player's jump action.
Stand Jumping Meters	Maximum height the player can reach when jumping from a standing position.
Stand Jumping Duration	The time it takes for the player to reach the maximum height when jumping from a standing position.
Crouch Jumping Meters	Maximum height the player can reach when jumping from a crouched position.
Crouch Jumping Duration	The time it takes for the player to reach the maximum height when jumping from a crouched position.
Weapon Touch	Settings for adjusting touchpad sensitivity and smoothing during weapon aiming.
X Sensitivity	Horizontal sensitivity of the touchpad for aiming.
Y Sensitivity	Vertical sensitivity of the touchpad for aiming.
Smooth	Enables or disables how smooth should be the touchpad input.
Smooth Time	Defines the duration over which touchpad input is smooth.

Procedural Bobbing

This Script Controls The Player Walk,Sprint,Jump and Aimed Bobbing Behaviour.




Fields	Info
First Person Controller Script	Player root gameobject containing 'FirstPersonController' script is to be placed into this field.
Player Manager Script	PlayerManager gameobject containing 'PlayerManager' script is to be placed into this field.
Bob Object	Gameobject to be bobbed is to be placed into this field.
Enable Procedural Hip Fire Idle	Toggle procedural Hip Fire Idle animation.

Enable Procedural Aimed Idle	Toggle procedural Aimed Idle animation.
Hip Fire Pos Value	Position offset values for the Hip Fire Idle pose.
Hip Fire Rot Value	Rotation offset values for the Hip Fire Idle pose.
Aimed Pos Value	Position offset values for the Aimed Idle pose.
Aimed Rot Value	Rotation offset values for the Aimed Idle pose.
Stand Hip Fire Idle Values	Bob values for Standing Hip Fire Idle.
Crouch Hip Fire Idle Values	Bob values for Crouching Hip Fire Idle.
Stand Aimed Idle Values	Bob values for Standing Aimed Idle.
Crouch Aimed Idle Values	Bob values for Crouching Aimed Idle.
Stationary Stand Hip Fire Reset Duration	Reset duration for Stationary Stand Hip Fire pose.
Stationary Crouch Hip Fire Reset Duration	Reset duration for Stationary Crouch Hip Fire pose.
Stationary Stand Aimed Reset Duration	Reset duration for Stationary Stand Aimed pose.
Stationary Crouch Aimed Reset Duration	Reset duration for Stationary Crouch Aimed pose.
Stand Sprint Reset Duration	Reset duration for Stand Sprint.
Crouch Sprint Reset Duration	Reset duration for Crouch Sprint.
Stand Walk Reset Duration	Reset duration for Stand Walk.
	Reset duration for Crouch Walk.

Crouch Walk Reset Duration	
Stand Jump Reset Duration	Reset duration for Stand Jump.
Crouch Jump Reset Duration	Reset duration for Crouch Jump.
Bob Stand Sprint Values	Bobbing values for Stand Sprint.
Bob Crouch Sprint Values	Bobbing values for Crouch Sprint.
Bob Stand Walk Values	Bobbing values for Stand Walk.
Bob Crouch Walk Values	Bobbing values for Crouch Walk.
Bob Aimed Stand Walk Values	Bobbing values for Aimed Stand Walk.
Bob Aimed Crouch Walk Values	Bobbing values for Aimed Crouch Walk.
Bob Stand Jump Values	Bobbing values for Stand Jump.
Bob Crouch Jump Values	Bobbing values for Crouch Jump.

Multiple Ambient Sounds Player This script, handles the playback of ambient sounds in the game. It supports playing sounds either randomly or sequentially, based on the 'PlaySoundsRandomly' field. Each sound can have unique properties such as volume, priority, loop behavior, and a time range for playback duration. The script uses a coroutine to manage the timing and playback of sounds, ensuring seamless transitions between them. It requires an 'AudioSource' component on the same GameObject to function properly and can be configured using the 'AmbientSoundProperties' list.



Fields	Info
Play Sounds Randomly Determines whether the ambient sounds should be played in random o	
Sound Name Name of the sound for identification purposes.	
Audio Clip To Play The audio clip to play for this ambient sound.	
Audio Volume Volume level for this audio clip (0 = muted, 1 = full volume).	
Loop Whether this audio clip should loop continuously when played.	

Audio Priority	The priority of this audio clip (0 = highest priority, 256 = lowest priority)
Minimum Time To Play This Sound	The minimum amount of time (in seconds) before this sound can start
Maximum Time To Play This Sound	The maximum amount of time (in seconds) before this sound can start
Ambient Sound Properties	List of ambient sound properties. Each entry defines the character