

Player Weapon Shooting Features Part-3


Introduction

This video will help you understand about player weapon script attached to the shooting point of the weapon.

Player Weapon Script

Player Weapon Script is the main script responsible for all kinds of weapons available to player, such as various kinds of firearms, grenades & melee weapons. It defines majority of aspects of weapons overall functionality & communicates with number of auxiliary scripts that are handling additional elements of the player weapons functionality.

You will find below some of the fields and their tooltips for the Player Weapon Script.



Fields	Info
RaycastShootingRange	Shooting range of the weapon if it uses raycast.

FullAutoFireRate	Affects the Weapon Fire Rate in both Raycast and projectile shooting functionality.
TargetDamagePerShot	Damage to target on shoot.
DefaultImpactEffectName	If the bullet hits on other colliders (e.g., road, houses), specifies which prefab to spawn from Object Pooler on that hit point (e.g., BulletHole).
MuzzleFlashRotatingObject	'MuzzleFlashRotator' game object needs to be dragged & dropped into this field.
MuzzleFlashRotatorMaxNegativeAngle	Value of maximal possible rotational angle offset of the MuzzleFlashRotator gameobject in negative Z axis per weapon shot.
MuzzleFlashRotatorMaxPositiveAngle	Value of maximal possible rotational angle offset of the MuzzleFlashRotator gameobject in positive Z axis per weapon shot.
WeaponCrosshair	This field is populated with an advanced crosshair UI element. If you want to use a simple crosshair, you can drag & drop it into this field instead.
RaycastShootingVisibleLayers	Specify what layers raycast shooting will be affected by. Unchecked layers will be ignored.
ForceFullAutoFire	If checked, weapon will shoot in full automatic mode.
IdleToAimedAnimationTransitionDelay	Value in seconds during which weapon idle animation clip inside the 'Idle' animator state will continue to be played before switching to the 'InitialPose' animator state.

BulletShellName	Bullet shell name inside the Object Pooler script.
ProjectileName	Name in this field should match the name of the respective field inside the Object Pooler script for shooting to function properly.
ProjectilesPerShot	Number of projectiles per shot if this weapon is using 'ProjectileShooting' (e.g., shotguns). Spread is defined in the 'BulletSpread' field.
ShootingOption	Select the shooting option: RaycastShootingWithTracers (tracers without damage, for visuals).
AddRaycastForce	If checked, will apply raycast force to targets with a Rigidbody (AI agents or non-AI game objects with Rigidbody attached), with random force between Min & Max values.
MinRaycastForceToAi	Minimal base force value multiplied by the values of all the fields below (except the last one related to non-AI targets).
MaxRaycastForceToAi	Maximal base force value multiplied by the values of all the fields below (except the last one related to non-AI targets).
RaycastForce	Details for applying raycast force for AI agents (force direction and magnitude). Non-AI game objects are handled by the 'NonAIGameObjectImpactForce' field.
WeaponPositionLerpSpeed	Linear interpolation speed between weapon idle and weapon reloading positions.
WeaponRotationLerpSpeed	Linear interpolation speed between weapon idle and weapon reloading rotations.
BulletSpread	

If you want to introduce bullet spread effect for each consecutive shot, set this field to change shooting point's rotation between specified min/max angles.