

NC2 on AWS Deployment Workflow
https://squasta.github.io
Updated : 27 July 2026
1-Setting up My Nutanix Account and activate NC2
The shared workspace should be used when activating the NC2 console, reserving license capacity for NC2, or activating the NC2 PAYG subscription. You can also join a shared workspace you have been invited to
1.1 Create a new shared workspace with the Account Admin Role
1.2 Activate PAYG Subscription
1.3 Configure License Capacity Reservation
A My Nutanix account allows you to subscribe to, access, and manage NC2
2- Setting up AWS Account and resources
An AWS user that can access AWS console and has create IAM user permission
An IAM User with 3 permissions
- IAMFullAccess
- AWS_ConfigRole
- AWSCloudFormationFullAccess
[Note : you can also pre create the 2 Nutanix roles]
Setting AWS vCPU Limits
(1 physical core = 2 vCPUs)
Reviewing SSH Key Pairs
3- Setting Up the networking Infra in AWS
Networking requirements:
- Connectivity between your on-prem datacenter and AWS Both DirectConnect and VPN are supported
IP ranges (CIDR) for AWS subnet used by NC2 on AWS
NC2 portal can also create new VPC, Subnet...
3.1- Manual workflow
Create an AWS VPC
CIDR requirements : between /16 and /23
Not allowed CIDRs : 192.168.5.0/24
Not allowed CIDRs : 10.100.0.0/16, 10.200.32.0/24
Create private / public subnets
Attach Internet Gateway
Create NAT Gateway
Configure route tables and routing
3.2- Interconnection
VPN Site to Site
Direct Connect
3.3- DNS resolution
3.4 Authorise outbound access on your firewall / proxy (optional)
List of protocols and domains
For Microservices Infrastructure (Flow Network)
4- Setting up the NC2 console
Add your AWS Account as a Cloud Account
CloudFormation Templates Customization
Deployment of a CloudFormation Stack that creates 2 IAM Roles
Nutanix-Clusters-High-Nc2-Cluster-Role-Prod --> EC2 instances
Nutanix-Clusters-High-Nc2-Orchestrator-Role-Prod --> Nutanix portal AWS Account
5-Creating a Nutanix Cluster
Supported AWS regions and Instances
Supported Instances tenancy types
Deployment Stages
6- Deploying or register a Prism Central (optional)
7- Configure Networking for UVM
Native AWS VPC integration
Creating and managing User VM Subnet(s) for External connectivity
Create a UVM Network (Subnet)
Add vNICs to a UVM
Enable inbound and outbound Internet access to UVMs with NAT Gateway
Enable inbound internet access to an application running on NC2 using an AWS load balancer
Flow Virtual Networking Configuration
Prism Central is mandatory for Flow Networking
Use rfc6598 for CIDR in external-subnet-nonat in transit VPC
8- Performing additional configuration after the cluster creation
Data Protection, administration
Cluster Management through NC2 portal
Configure Data at Rest encryption
Configure Disaster Recovery
MST with Pilot Light
Cluster Protect (AWS Native networking only)
Microsegmentation (FNS NG)
Logging into Cluster using SSH
Hibernate/Resume
Create a S3 Gateway Endpoint