Claude Code Keypad

Press the encoder to switch layers. Key numbers run 0-11 from the top-left, OLED at the top.

DRIVE steer the focused session

OLED shows layer name and key labels

0	1	2
ESC Interrupt `Esc`	**MODE** Cycle permission mode `Shift+Tab`	**REWIND** Rewind menu `Esc, Esc`
3	4	5
YES Approve once `1`	**ALWAYS** Approve always `2`	**NO** Deny `3`
6	7	8
TAB Autocomplete `Tab`	**LOG** Transcript view `Ctrl+O`	**COMPACT** Compact context `types /compact`
9	10	11
ENTER Submit `Enter`	**TALK** Speech to text (hold) `holds Right Option`	**BG** Background task `Ctrl+B, Ctrl+B`

Encoder

Turn right	Down	`Down arrow`
Turn left	Up	`Up arrow`
Press	Next layer	`Fleet`

FLEET move between herdr agents

OLED shows layer name and key labels

0	1	2
A1 Focus agent 1 `pfx Shift+1`	**A2** Focus agent 2 `pfx Shift+2`	**A3** Focus agent 3 `pfx Shift+3`
3	4	5
A4 Focus agent 4 `pfx Shift+4`	**A5** Focus agent 5 `pfx Shift+5`	**A6** Focus agent 6 `pfx Shift+6`
6	7	8
ATTN Agent needing attention `pfx O`	**NEW** New Claude Code tab `pfx Shift+C`	**RESUME** Resume in new tab `pfx Shift+A`
9	10	11
ZOOM Zoom pane `pfx Z`	**LAST** Last focused pane `pfx ;`	**ENTER** Submit `Enter`

Encoder

Turn right	Next agent	`pfx .`
Turn left	Previous agent	`pfx ,`
Press	Next layer	`Drive`

Key colors

stop · decision / attention · mode and navigation · voice · submit · utility

herdr setup

- pfx = herdr prefix, Ctrl+B by default. HERDR_PREFIX in code.py must match keys.prefix in herdr's config.toml.
- A1-A6, next/previous agent and LAST need the [keys] lines from MacroPad Layout Studio.
- NEW and RESUME need the studio's [[keys.command]] blocks, plus jq on the PATH.
- Agent numbers follow the order of the herdr sidebar. ATTN uses herdr's built-in notification jump and needs no config.
- Apply config changes with: herdr server reload-config


Keycap inserts · 12 mm

50 mm

Print at 100% (Actual size, no scaling). Check the 50 mm bar, then cut on the crop marks.

Both layers

Drive on top, Fleet below. Use these for one set of caps.




Drive only

One legend per key.




Fleet only

One legend per key.



Spares

A second Both-layers set for miscuts.



Blanks

Handwrite new legends as the layout changes.

