```
ec2-user@ip-172-31-42-47:~> openssl passwd -6
Password:
Verifying - Password:
$6$Ij/2XLX8oo5z3M89$.0UsitdBYj24VJhjhICmcg7a5Hn/RFY9FC9fneZjoS1AU98cZATwmJxI6AZ9aZeZ.3MTs5pWMaEB9IKdDE8Qh1
ec2-user@ip-172-31-42-47:~> ^C
```

```
ec2-user@ip-172-31-42-47:~> ansible all -i slaves.txt -m ansible.builtin.user -a "name=giri password=$6$Ij/2XLX8oo5z3M89$.0UsitdBYj24VJhjhICmcg7a5Hn/RFY9FC9f
neZjoS1AU98cZATwmJxI6AZ9aZeZ.3MTs5pWMaEB9IKdDE8Qh1" -b

[WARNING]: Host '172.31.40.47' is using the discovered Python interpreter at '/usr/bin/python3.13', but future installation of another Python interpreter cou
ld cause a different interpreter to be discovered. See https://docs.ansible.com/ansible-core/2.21/reference_appendices/interpreter_discovery.html for more in
formation.
[WARNING]: The input password appears not to have been hashed. The 'password' argument must be encrypted for this module to work properly.
172.31.40.47 | CHANGED => {
    "ansible_facts": {
        "discovered_interpreter_python": "/usr/bin/python3.13"
    },
    "changed": true,
    "comment": "",
    "create_home": true,
    "group": 1005,
    "groups": "",
    "home": "/home/giri",
    "name": "giri",
    "password": "NOT_LOGGING_PASSWORD",
    "shell": "/bin/bash",
    "state": "present",
    "system": false,
    "uid": 1005
}
[WARNING]: Host '172.31.35.54' is using the discovered Python interpreter at '/usr/bin/python3.13', but future installation of another Python interpreter cou
ld cause a different interpreter to be discovered. See https://docs.ansible.com/ansible-core/2.21/reference_appendices/interpreter_discovery.html for more in
formation.
172.31.35.54 | CHANGED => {
    "ansible_facts": {
        "discovered_interpreter_python": "/usr/bin/python3.13"
    },
    "changed": true,
    "comment": "",
    "create_home": true,
    "group": 1005,
    "groups": "",
    "home": "/home/giri",
    "name": "giri",
    "password": "NOT_LOGGING_PASSWORD",
    "shell": "/bin/bash",
```

```
ec2-user@ip-172-31-42-47:~> ansible nginx -i slaves.txt -m ping
[WARNING]: Host '172.31.35.54' is using the discovered Python interpreter at '/usr/bin/python3.13', but future installation of another Python interpreter c
ld cause a different interpreter to be discovered. See https://docs.ansible.com/ansible-core/2.21/reference_appendices/interpreter_discovery.html for more
formation.
172.31.35.54 | SUCCESS => {
    "ansible_facts": {
        "discovered_interpreter_python": "/usr/bin/python3.13"
    },
    "changed": false,
    "ping": "pong"
}
ec2-user@ip-172-31-42-47:~>
```

```
ec2-user@ip-172-31-42-47:~> ansible all -i slaves.txt -a "uptime"
[WARNING]: Host '172.31.35.54' is using the discovered Python interpreter at '/usr/bin/python3.13', but future installation of another Python interpreter cou
ld cause a different interpreter to be discovered. See https://docs.ansible.com/ansible-core/2.21/reference_appendices/interpreter_discovery.html for more in
formation.
172.31.35.54 | CHANGED | rc=0 >>
 09:41:44  up   0:30,  1 user,  load average: 0.11, 0.07, 0.01
[WARNING]: Host '172.31.43.123' is using the discovered Python interpreter at '/usr/bin/python3.13', but future installation of another Python interpreter co
uld cause a different interpreter to be discovered. See https://docs.ansible.com/ansible-core/2.21/reference_appendices/interpreter_discovery.html for more i
nformation.
172.31.43.123 | CHANGED | rc=0 >>
 09:41:44  up   0:30,  1 user,  load average: 0.01, 0.02, 0.00
[WARNING]: Host '172.31.40.47' is using the discovered Python interpreter at '/usr/bin/python3.13', but future installation of another Python interpreter cou
ld cause a different interpreter to be discovered. See https://docs.ansible.com/ansible-core/2.21/reference_appendices/interpreter_discovery.html for more in
formation.
172.31.40.47 | CHANGED | rc=0 >>
 09:41:44  up   0:30,  1 user,  load average: 0.00, 0.00, 0.00
ec2-user@ip-172-31-42-47:~>
```

```
ec2-user@ip-172-31-42-47:~> ansible all -i slaves.txt -a "uname -a"
[WARNING]: Host '172.31.40.47' is using the discovered Python interpreter at '/usr/bin/python3.13', but future installation of another Python interpreter cou
ld cause a different interpreter to be discovered. See https://docs.ansible.com/ansible-core/2.21/reference_appendices/interpreter_discovery.html for more in
formation.
172.31.40.47 | CHANGED | rc=0 >>
Linux ip-172-31-40-47 6.12.0-160000.29-default #1 SMP PREEMPT_DYNAMIC Fri May  1 12:45:19 UTC 2026 (66d7b47) x86_64 x86_64 x86_64 GNU/Linux
[WARNING]: Host '172.31.35.54' is using the discovered Python interpreter at '/usr/bin/python3.13', but future installation of another Python interpreter cou
ld cause a different interpreter to be discovered. See https://docs.ansible.com/ansible-core/2.21/reference_appendices/interpreter_discovery.html for more in
formation.
172.31.35.54 | CHANGED | rc=0 >>
Linux ip-172-31-35-54 6.12.0-160000.29-default #1 SMP PREEMPT_DYNAMIC Fri May  1 12:45:19 UTC 2026 (66d7b47) x86_64 x86_64 x86_64 GNU/Linux
[WARNING]: Host '172.31.43.123' is using the discovered Python interpreter at '/usr/bin/python3.13', but future installation of another Python interpreter co
uld cause a different interpreter to be discovered. See https://docs.ansible.com/ansible-core/2.21/reference_appendices/interpreter_discovery.html for more i
nformation.
172.31.43.123 | CHANGED | rc=0 >>
Linux ip-172-31-43-123 6.12.0-160000.29-default #1 SMP PREEMPT_DYNAMIC Fri May  1 12:45:19 UTC 2026 (66d7b47) x86_64 x86_64 x86_64 GNU/Linux
ec2-user@ip-172-31-42-47:~>
```

```
ec2-user@ip-172-31-42-47:~> vi slaves.txt
ec2-user@ip-172-31-42-47:~> vi ansible.cfg
ec2-user@ip-172-31-42-47:~> ansible all -i slaves.txt -m ping
```

```
ec2-user@ip-172-31-42-47:~> ansible all -i slaves.txt -m ping
[WARNING]: Host '172.31.40.47' is using the discovered Python interpreter at '/usr/bin/python3.13', but future installation of another Python interpreter cou
ld cause a different interpreter to be discovered. See https://docs.ansible.com/ansible-core/2.21/reference_appendices/interpreter_discovery.html for more in
formation.
172.31.40.47 | SUCCESS => {
    "ansible_facts": {
        "discovered_interpreter_python": "/usr/bin/python3.13"
    },
    "changed": false,
    "ping": "pong"
}
[WARNING]: Host '172.31.43.123' is using the discovered Python interpreter at '/usr/bin/python3.13', but future installation of another Python interpreter co
uld cause a different interpreter to be discovered. See https://docs.ansible.com/ansible-core/2.21/reference_appendices/interpreter_discovery.html for more i
nformation.
172.31.43.123 | SUCCESS => {
    "ansible_facts": {
        "discovered_interpreter_python": "/usr/bin/python3.13"
    },
    "changed": false,
    "ping": "pong"
}
[WARNING]: Host '172.31.35.54' is using the discovered Python interpreter at '/usr/bin/python3.13', but future installation of another Python interpreter cou
ld cause a different interpreter to be discovered. See https://docs.ansible.com/ansible-core/2.21/reference_appendices/interpreter_discovery.html for more in
formation.
172.31.35.54 | SUCCESS => {
    "ansible_facts": {
        "discovered_interpreter_python": "/usr/bin/python3.13"
    },
    "changed": false,
    "ping": "pong"
}
ec2-user@ip-172-31-42-47:~>
```