```
dell@DESKTOP-BUKE0VT:~$ su - user2
Password:
Welcome to Ubuntu 26.04.1 LTS (GNU/Linux 6.18.54.1-microsoft-standard-WSL2 x86_64)

 * Documentation:  https://docs.ubuntu.com
 * Management:     https://landscape.canonical.com
 * Support:        https://ubuntu.com/pro

 System information as of Wed Oct 21 23:29:55 +05 2026

  System load:  0.0                Processes:             61
  Usage of /:   0.1% of 1006.85GB  Users logged in:       0
  Memory usage: 6%                 IPv4 address for eth0: 172.23.183.6
  Swap usage:   0%

  => /usr/lib/linux-tools/6.18.54.1-microsoft-standard-WSL2 is using 100.0% of
     96MB


This message is shown once a day. To disable it please create the
/home/user2/.hushlogin file.
user2@DESKTOP-BUKE0VT:~$ sudo passwd user2
sudo: I'm sorry user2. I'm afraid I can't do that
user2@DESKTOP-BUKE0VT:~$ whoami
user2
user2@DESKTOP-BUKE0VT:~$ chfn
Password:
Changing the user information for user2
Enter the new value, or press ENTER for the default
        Full Name: Sitaieah
        Room Number [45]: 33
        Work Phone [309u35u435]: 03945034985
        Home Phone [35945802545]: 3940585943
user2@DESKTOP-BUKE0VT:~$ exit
logout
dell@DESKTOP-BUKE0VT:~$ tail -n 3 /etc/passwd
polkitd:x:987:987:User for polkitd:/:/usr/sbin/nologin
dell:x:1000:1000::/home/dell:/bin/bash
user2:x:1001:1001:Sitaieah,33,03945034985,3940585943,none:/home/user2:/bin/bash
dell@DESKTOP-BUKE0VT:~$ sudo pkill -KILL -u user2
[sudo: authenticate] Password:
sudo: Authentication failed, try again.
[sudo: authenticate] Password:
dell@DESKTOP-BUKE0VT:~$ sudo deluser --remove-home user2
dell@DESKTOP-BUKE0VT:~$ tail -n 3 /etc/passwd
landscape:x:101:103::/var/lib/landscape:/usr/sbin/nologin
polkitd:x:987:987:User for polkitd:/:/usr/sbin/nologin
dell:x:1000:1000::/home/dell:/bin/bash
dell@DESKTOP-BUKE0VT:~$
```