# GOONVIZ × Akai MPD32

Load preset 18 'ArkaosVJ' on the MPD32 (PRESET button, then the dial). Its knobs/faders/switches send CC 1-72 and its pads latch.

## PAD BANK A press PAD BANK A

| | | | |
|---|---|---|---|
| A13 **13** Hyper Crystal | A14 **14** Hypergyroid | A15 **15** Spirit Mirror (video) | A16 **16** Video Melt (video) |
| A9 **9** Bioluminescence | A10 **10** Julia Bloom | A11 **11** Mandelbox | A12 **12** Apollonian Foam |
| A5 **5** Crystal Caverns | A6 **6** Tesseract Lattice | A7 **7** Apollonian Lace | A8 **8** Wormhole |
| A1 **1** Astral Mandala | A2 **2** Fractal Temple | A3 **3** Liquid Spirit | A4 **4** Quaternion Julia |

## PAD BANK B press PAD BANK B

| | | | |
|---|---|---|---|
| B13 **Snap 5** SHIFT + hit = save | B14 **Snap 6** SHIFT + hit = save | B15 **Snap 7** SHIFT + hit = save | B16 **Snap 8** SHIFT + hit = save |
| B9 **Snap 1** SHIFT + hit = save | B10 **Snap 2** SHIFT + hit = save | B11 **Snap 3** SHIFT + hit = save | B12 **Snap 4** SHIFT + hit = save |
| B5 **◀ Prev** | B6 **Next ▶** | B7 **Tap beat** | B8 **Flash** |
| B1 **17** Video Fractal (video) | B2 **Random preset** | B3 **Randomize FX** | B4 **Reset knobs** |

## TRANSPORT

| | | | | |
|---|---|---|---|---|
| ◀◀ **◀ Prev** | ▶▶ **Next ▶** | ■ STOP **BLACKOUT** | ▶ PLAY **Autopilot** | ● REC **Randomize FX** |

## CONTROL BANK A default bank

KNOBS

| K1 | K2 | K3 | K4 | K5 | K6 | K7 | K8 |
|---|---|---|---|---|---|---|---|
| **Knob A** preset's own control | **Knob B** preset's own control | **Knob C** preset's own control | **Knob D** preset's own control | **Speed** time rate | **Zoom** scale the scene | **Palette** 10 colour sets | **Hue** master colour shift |

FADERS

| F1 | F2 | F3 | F4 | F5 | F6 | F7 | F8 |
|---|---|---|---|---|---|---|---|
| **Trails** feedback amount | **Trail zoom** tunnel in / out | **Trail spin** swirl left / right | **Trail hue** rainbow drift | **Glow** bloom haze | **Kaleido** off → 12 mirrors | **Camera mix** blend live video | **MASTER** brightness |

SWITCHES

| S1 | S2 | S3 | S4 | S5 | S6 | S7 | S8 |
|---|---|---|---|---|---|---|---|
| **Autopilot** | **Freeze** | **Camera on/off** | **Strobe** flash on beats | **Invert** negative image | **Overlay** | **BLACKOUT** | **SHIFT** |

## CONTROL BANK B press CONTROL BANK until B is lit

KNOBS

| K1 | K2 | K3 | K4 | K5 | K6 | K7 | K8 |
|---|---|---|---|---|---|---|---|
| **Warp** liquid distortion | **Chroma** RGB split | **Saturation** grey → vivid | **Contrast** | **Audio react** how hard sound hits | **Strobe** flash on beats | **Zoom** scale the scene | **Speed** time rate |

FADERS

| F1 | F2 | F3 | F4 | F5 | F6 | F7 | F8 |
|---|---|---|---|---|---|---|---|
| **Knob A** preset's own control | **Knob B** preset's own control | **Knob C** preset's own control | **Knob D** preset's own control | **360 view** flat · look · planet · hole | **360 spin** pan the room ◀ ▶ | **Autopilot** intensity: calm → wild | **Audio react** how hard sound hits |

## PAD BANK C press PAD BANK C

| | | | |
|---|---|---|---|
| C13 **30** Chrome Lattice | C14 **31** Hyperbolic Honeycomb | C15 | C16 |
| C9 **26** Nautilus | C10 **27** Alien Jungle | C11 **28** Fractal Cathedral | C12 **29** Mandelbulb Bloom |
| C5 **22** Mandala Mandelbox | C6 **23** Prism Shards | C7 **24** Cicada Wing | C8 **25** Mycelium |
| C1 **18** Hyperbolic Mandala | C2 **19** Kaleido Bloom | C3 **20** Crystal Kaleidoscope | C4 **21** Kaleido Tunnel |

■ show-critical ▢ action ▢ snapshot (hold SHIFT to save) ▢ preset  Switches: on = engaged · works in momentary (hold) or toggle mode

# **GOONVIZ** presets & knobs A–D

Knobs K1–K4 (and bank B faders F1–F4) change meaning per preset.

| # | PRESET | A (K1) | B (K2) | C (K3) | D (K4) |
|---|---|---|---|---|---|
| 1 | **Astral Mandala** | petals | layers | filigree | color drift |
| 2 | **Fractal Temple** | symmetry | spread | fold angle | color |
| 3 | **Liquid Spirit** | turbulence | filaments | filament count | color |
| 4 | **Quaternion Julia** | shape | 4th-dimension slice | detail (heavy) | color |
| 5 | **Crystal Caverns** | cave scale | wall thickness | quality (Pi: keep low) | color |
| 6 | **Tesseract Lattice** | beam thickness | 4D spin | beat snap | color |
| 7 | **Apollonian Lace** | inversion | drift | lace brightness | color |
| 8 | **Wormhole** | twist | segments | ornament | color |
| 9 | **Bioluminescence** | cell size | wobble | nuclei | color |
| 10 | **Julia Bloom** | seed angle | morph speed | detail | color |
| 11 | **Mandelbox** | fold scale | camera distance | detail (heavy) | color |
| 12 | **Apollonian Foam** | bubble size | drift | detail (heavy) | color |
| 13 | **Hyper Crystal** | fold angle | 4th-dimension slice | facets | color |
| 14 | **Hypergyroid** | cave scale | 4D spin | wall thickness | color |
| 15 | **Spirit Mirror (video)** | edge gain | aura | body fill | color |
| 16 | **Video Melt (video)** | melt | flow speed | contours | color |
| 17 | **Video Fractal (video)** | folds | spread | tint | color |
| 18 | **Hyperbolic Mandala** | polygon sides | meeting at each corner | flow | color |
| 19 | **Kaleido Bloom** | petals | layers | inner detail | color |
| 20 | **Crystal Kaleidoscope** | cell size | turbulence | camera (0 = none) | color |
| 21 | **Kaleido Tunnel** | segments | rings per depth | ornament | color |
| 22 | **Mandala Mandelbox** | fold scale | symmetry | detail | color |
| 23 | **Prism Shards** | shard size | refraction | seed light | color |
| 24 | **Cicada Wing** | wing spread | vein density | iridescence | color |
| 25 | **Mycelium** | network scale | thread sharpness | pulse speed | color |
| 26 | **Nautilus** | spiral growth | chambers | nacre sheen | color |
| 27 | **Alien Jungle** | leaf size | sway | fireflies | color |
| 28 | **Fractal Cathedral** | hall width | twist | beat snap | color |
| 29 | **Mandelbulb Bloom** | power | orbit distance | detail (heavy) | color |
| 30 | **Chrome Lattice** | tube thickness | ripple | beat snap | color |
| 31 | **Hyperbolic Honeycomb** | edge thickness | look around | stained glass | color |

## SHOW CHECKLIST

1. Power the MPD32 and load preset **18 ArkaosVJ** before starting GoonViz.
2. Pads latch in that preset: every hit counts, so ignore the pad lights.
3. Bring MASTER (F8) up. Keep a finger near **BLACKOUT** (S7) or ■ STOP.
4. **Autopilot** (S1 / ▶ PLAY) switches presets and keeps every knob moving. Bank B F7 sets intensity, from calm to wild. Any knob you touch, autopilot leaves alone until the next switch.
5. Save looks: S8 SHIFT on, hit a blue snapshot pad, SHIFT off.

## IF SOMETHING'S OFF

- Pads do nothing: on the Pi run `run.py --learn-pads` and hit the pads in order.
- Change any control: plug in a keyboard, `H`, ↑↓ to choose, `L`, move the control.
- Then reprint: `python tools/make_cheatsheet.py`
- No reaction to music: check the audio input; Audio react is bank B K5.

## KEYBOARD

`←` `→` preset · `R` randomize · `B` blackout · `A` autopilot · `Space` flash · `H` overlay · `F1`–`F8` snapshots · `Esc` quit