AVAPS Drop Log

Project: _____ Mission: Ida Flight ID: 20210827N1

Take Off: _____ Landing: _____ Flt Dir: Holmes Launcher S/N: 2

Drop #	Sonde Serial #	Rcvr #	Press Offset	Launch Time	Operator	Charge $$ To	Comments	Good ?
1	204 120 634	1	Ø	—	JH	NWS	No LD	
2	204 270 047	2	Ø	0609			backup	✓
3	204 530 461	3	Ø	0619				✓
4	203 850 400	4	Ø	0632				✓
5	205 050 321	1	Ø	0646				✓
6	204 650 401	2	Ø	0705				✓
7	205 050 261	3	Ø	0719			fast fall	
8	205 050 380	4	Ø	0721			backup	✓
9	204 840 556	1	Ø	0733			fast fall	
10	205 050 286	2	Ø	0735			backup	✓
11	205 050 382	3	Ø	0754				✓
12	205 050 103	4	Ø	0807				✓
13	204 650 381	1	Ø	0824				✓
14	204 521 394	2	Ø	0834				✓
15	204 450 350	3	Ø	0844				✓
16	204 530 390	4	Ø	0857				✓
17	204 850 437	1	Ø	0912				✓
18	204 530 813	2	Ø	0922				✓
19	204 640 858	3	Ø	0931				✓
20	204 521 395	4	Ø	0945				✓
21	204 520 778	1	Ø	0954				✓
22	204 520 796	2	Ø	1005				✓
23	204 840 568	3	-0.6	1015				✓
24	205 050 313	4	Ø	1025				✓
25	204 521 376	1	Ø	1041				✓
26	205 050 111	2	Ø	1056				✓
27	204 850 435	3	Ø	1104				✓
28	204 850 436	4	Ø	1114				✓
29	204 840 701	1	Ø	1123				✓
30	204 521 393	2	Ø	1131				✓
31	204 521 379	3	Ø	1140				✓

Drop #	Sonde Serial #	Rcvr #	Press Offset	Launch Time	Operator	Charge $$ To	Comments	Good ?
32	204 840 699	4	Ø	1156	JEH	NWS		✓
33	204 850 200	1	Ø	1211				✓
34	204 820 494	2	Ø	1223				✓
35	204 840 566	3	Ø	1232				✓
36								
37								
38								
39								
40								
41								
42								
43								
44								
45								
46								
47								
48								
49								
50								

Drop Station Operator Notes

Charge $$ To Options (DO NOT USE FUNDING CODES):
AOC, NWS, HRD, NESDIS, IR/SST, AR, STAN (Stanford), SAT (JPSS/NESDIS/HRD)

AVAPS Pre-Flight Check:

- If time-permits, verify cabin pressure sensor w/ lab standard
- Start AVAPS., then start Soundings and set the Project Name and Full Flight ID (example: 20120823N2).
- Verify the Frequency band allocation as required:
  Band A: 53rd WRS - Band B: N42RF - Band C: N43RF - Band D: N49RF - Band E: Unallocated
- Select the **GPS Reference** tab from the **Soundings Displays** page and verify good GPS data
- Perform a prelaunch check on each channel, look for reasonable data and no CRC error status lights.
- Verify data is available on Remote AVAPS, then terminate the sonde.
- Verify the AVAPS Data mission folder has been created
- Verify AVAPS PC Time is correct – if time is off by >4sec, no data will display
- Early launch detects are caused usually by remanufactured sondes with the chute riser line not properly coiled below the PCB ear. This may also cause fast falls. If this is suspected, repack the riser line as time permits
- Perform RH Regeneration on all sondes – Multiple RD41 sondes may be processed at once

AVAPS Launch:

- Select a sonde frequency in the Green band and away from other sondes
- Enter sonde pressure error offset if 0.4mB or greater using cabin pressure sensor – warning, this can not be used during a climb
- If the Cal lab pressure standard and the cabin pressure standard match, apply pressure offset +/- 0.1 mB
- Wait until GPS available (green) on the pre-launch screen before continuing.
- Select "begin data collection" and verify good data with winds prior to putting sonde in launch tube
- On N42 & N43, remove about ½ of the ribbon. Do not shorten the ribbon on N49. Loosen ribbon and extend end of ribbon to near, but not over, the sensor end of the sonde. Place excess orange tape on end of ribbon to form a pocket.
- Place the sonde in the launch tube, sensor arm up, with the power pin socket facing right
- Verify the sonde is actively tracking GPS data prior to launch and no early launch detect

AVAPS Drop Log

Project: TS Mission: IDA Flight ID: 20210827N2

Take Off: _____ Landing: _____ Flt Dir: Quinn/Rich Launcher S/N: _____

Drop #	Sonde Serial #	Rcvr #	Press Offset	Launch Time	Operator	Charge $$ To	Comments	Good ?
1	204160653	1	0	1800	AJP	NWS		✓
2	204840411	2	0	1814				✓
3	204640457	3	0	1827				✓
4	204530499	4	0	1839				✓
5	204820160	1	0	1854				✓
6	204530458	2	0	1909				✓
7	204621171	3	0	1926				✓
8	205050255	4	0	1949				✓
9	204770519	1	0	2005				✓
10	205050262	2	0	2016				✓
11	205050309	3	0	2026				✓
12	204840421	4	0	2035				✓
13	204520798	1	0	2047				✓
14	204840409	2	0	2101				✓
15	204770386	3	0	2116				✓
16	204640854	4	0	2131				✓
17	205050325	1	0	2141				✓
18	204850438	2	0	2157				✓
19	204840675	3	0	2206				✓
20	204610867	4	0	2221				✓
21	204620014	1	0	2231				✓
22	204840425	2	0	2244				✓
23	204850557	3	0	2255				✓
24	205050268	4	0	2306				✓
25	204770517	1	0	2315				✓
26	204540656	2	0	2327				✓
27	204770527	3	0	2337				✓
28	204621173	4	0	2352				✓
29	204770527	1	0	0000				✓
30	204260650	2	0	0009				✓
31	204610673	3	0	0018				✓

Drop #	Sonde Serial #	Rcvr #	Press Offset	Launch Time	Operator	Charge $$ To	Comments	Good ?
32	204610678	4	0	0027	1	1		✓
33	204621174	1	0	0036				✓
34								
35								
36								
37								
38								
39								
40								
41								
42								
43								
44								
45								
46								
47								
48								
49								
50								

Drop Station Operator Notes

Charge $$ To Options (DO NOT USE FUNDING CODES):
AOC, NWS, HRD, NESDIS, IR/SST, AR, STAN (Stanford), SAT (JPSS/NESDIS/HRD)

AVAPS Pre-Flight Check:

- If time-permits, verify cabin pressure sensor w/ lab standard
- Start AVAPS., then start Soundings and set the Project Name and Full Flight ID (example: 20120823N2).
- Verify the Frequency band allocation as required:
  Band A: 53rd WRS - Band B: N42RF - Band C: N43RF - Band D: N49RF - Band E: Unallocated
- Select the **GPS Reference** tab from the **Soundings Displays** page and verify good GPS data
- Perform a prelaunch check on each channel, look for reasonable data and no CRC error status lights.
- Verify data is available on Remote AVAPS, then terminate the sonde.
- Verify the AVAPS Data mission folder has been created
- Verify AVAPS PC Time is correct – if time is off by >4sec, no data will display
- Early launch detects are caused usually by remanufactured sondes with the chute riser line not properly coiled below the PCB ear. This may also cause fast falls. If this is suspected, repack the riser line as time permits
- Perform RH Regeneration on all sondes – Multiple RD41 sondes may be processed at once

AVAPS Launch:

- Select a sonde frequency in the Green band and away from other sondes
- Enter sonde pressure error offset if 0.4mB or greater using cabin pressure sensor – warning, this can not be used during a climb
- If the Cal lab pressure standard and the cabin pressure standard match, apply pressure offset +/- 0.1 mB
- Wait until GPS available (green) on the pre-launch screen before continuing.
- Select "begin data collection" and verify good data with winds prior to putting sonde in launch tube
- On N42 & N43, remove about ½ of the ribbon. Do not shorten the ribbon on N49. Loosen ribbon and extend end of ribbon to near, but not over, the sensor end of the sonde. Place excess orange tape on end of ribbon to form a pocket.
- Place the sonde in the launch tube, sensor arm up, with the power pin socket facing right
- Verify the sonde is actively tracking GPS data prior to launch and no early launch detect

AVAPS Drop Log

Project: _____ Mission: Ida Flight ID: 20210828N1

Take Off: _____ Landing: _____ Flt Dir: Holmes Launcher S/N: 2

Drop #	Sonde Serial #	Rcvr #	Press Offset	Launch Time	Operator	Charge $$ To	Comments	Good ?
1	204 650 369	1	Ø	0547	JEH	NWS		✓
2	204 770 389	2	Ø	0559				✓
3	204 610 676	3	Ø	0611				✓
4	204 540 541	4	Ø	0628				✓
5	204 540 655	1	Ø	0641				✓
6	204 950 419	2	Ø	0657				✓
7	204 550 286	3	Ø	0701				✓
8	204 621 169	4	Ø	0715				✓
9	204 540 645	1	Ø	0728				✓
10	204 770 388	2	Ø	0736				✓
11	204 650 344	3	Ø	0752				✓
12	204 770 387	4	Ø	0806				✓
13	204 840 424	1	Ø	0816				✓
14	204 403 022	2	Ø	0825				✓
15	204 621 167	3	Ø	0835				✓
16	203 431 786	4	-1.5	0846				✓
17	192 620 165	1	-0.6	858				✓
18	204 031 074	2	-0.7	0911				✓
19	203 431 521	3	-1.4	0919				✓
20	203 830 804	4	-1.0	0929				✓
21	204 530 459	1	Ø	0939				✓
22	204 530 469	2	Ø	0949				✓
23	204 530 457	3	Ø	1003				✓
24	204 850 201	4	Ø	1022				✓
25	204 530 462	1	Ø	1033				✓
26	204 241 113	2	Ø	1042				✓
27	204 830 017	3	Ø	1100				✓
28	204 830 641	4	Ø	1108				✓
29	204 820 342	1	Ø	1117				✓
30	204 820 337	2	Ø	1127				✓
31	205 050 112	3	Ø	1135				✓

Drop #	Sonde Serial #	Rcvr #	Press Offset	Launch Time	Operator	Charge $$ To	Comments	Good ?
32	204 640 096	4	Ø	1147	JEH	NWS		
33								
34								
35								
36								
37								
38								
39								
40								
41								
42								
43								
44								
45								
46								
47								
48								
49								
50								

Drop Station Operator Notes

Charge $$ To Options (DO NOT USE FUNDING CODES):
AOC, NWS, HRD, NESDIS, IR/SST, AR, STAN (Stanford), SAT (JPSS/NESDIS/HRD)

AVAPS Pre-Flight Check:

- If time-permits, verify cabin pressure sensor w/ lab standard
- Start AVAPS., then start Soundings and set the Project Name and Full Flight ID (example: 20120823N2).
- Verify the Frequency band allocation as required:
  Band A: 53rd WRS - Band B: N42RF - Band C: N43RF - Band D: N49RF - Band E: Unallocated
- Select the **GPS Reference** tab from the **Soundings Displays** page and verify good GPS data
- Perform a prelaunch check on each channel, look for reasonable data and no CRC error status lights.
- Verify data is available on Remote AVAPS, then terminate the sonde.
- Verify the AVAPS Data mission folder has been created
- Verify AVAPS PC Time is correct – if time is off by >4sec, no data will display
- Early launch detects are caused usually by remanufactured sondes with the chute riser line not properly coiled below the PCB ear. This may also cause fast falls. If this is suspected, repack the riser line as time permits
- Perform RH Regeneration on all sondes – Multiple RD41 sondes may be processed at once

AVAPS Launch:

- Select a sonde frequency in the Green band and away from other sondes
- Enter sonde pressure error offset if 0.4mB or greater using cabin pressure sensor – warning, this can not be used during a climb
- If the Cal lab pressure standard and the cabin pressure standard match, apply pressure offset +/- 0.1 mB
- Wait until GPS available (green) on the pre-launch screen before continuing.
- Select "begin data collection" and verify good data with winds prior to putting sonde in launch tube
- On N42 & N43, remove about ½ of the ribbon. Do not shorten the ribbon on N49. Loosen ribbon and extend end of ribbon to near, but not over, the sensor end of the sonde. Place excess orange tape on end of ribbon to form a pocket.
- Place the sonde in the launch tube, sensor arm up, with the power pin socket facing right
- Verify the sonde is actively tracking GPS data prior to launch and no early launch detect