AVAPS Drop Log

Project: _____ Mission: Hur. LARRY Flight ID: 20210905N1

Take Off: 0857 Z Landing: _____ Flt Dir: KALEN/PATRISH Launcher S/N: 02

Drop #	Sonde Serial #	Rcvr #	Press Offset	Launch Time	Operator	Charge $$ To	Comments	Good ?
1	2044 200 92	1	-0.3	0916	JG	STAN	PHX	✓
2	2042 60886	2	-0.3	0927	JG	STAN		✓
3	204 330 602	3	-0.4	0937	JG	STAN		✓
4	204820 338	4	-0.1	0947	JG	STAN		✓
5	204310003	1	0	0957	JG	STAN		✓
6	204820 135	2	0	1008	JG	STAN		✓
7	204310001	3	-0.2	10.18	JG	STAN		✓
8	204 24 131	4	-0.3	10 29	JG	STAN	BAD PTH	
9	204 820 120	1	-0.4	10.30	JG	HRD	BACKUP Changed to STAN per Dunion Email	
10	204 260 889	2	0.0	1038	JG	STAN		
11	204 330 644	3	-0.2	1043	JG	STAN		
12	204 482 111	5	-0.1	1047	GABE	STAN		
13	204 482 137	6	-0.1	1056	GABE	STAN		
14	204 310 018	7	-0.3	1104	GABE	STAN		
15	204 530 395	8	0	1112	GABE	STAN		
16	204 530 460	1	0	1119	JG	STAN		
17	204 530 492	2	-0.1	1126	JG	STAN		
18	204 840 697	3	-0.2	1132	JG	STAN	NO GPS #1	
19	204 310 013	4	-0.3	1133	JG	HRD	BACKUP Changed to STAN per Dunion Email	
20	204 820 136	1	0	1141	JG	STAN		
21	210 620 036	5	-0.2	1149	JG	STAN		
22	210 240 802	6	-0.3	1159	JG	STAN		
23	204 241 114	2	-0.2	1209	JG	STAN		
24	204 650 397	3	-0.3	1214	JG	STAN		
25	204 330 601	4	-0.3	1220	JG	STAN		
26	204 830 040	1	-0.2	1228	JG	HRD		
27	204 530 471	2	-0.1	1236	JG	HRD		
28	204 310 017	3	-0.2	1241	JG	HRD		
29	204 820 134	4	+0.1	1250	JG	HRD		
30	204 820 123	1	-0.1	1257	JG	HRD		
31	204 530 408	5	+0.3	1303	JG	HRD		

1-25 STAN
26-36 HRD

#1 GPS CAME IN LATE.
#' LABELED GOOD ON LOG.

Drop #	Sonde Serial #	Rcvr #	Press Offset	Launch Time	Operator	Charge $$ To	Comments	Good ?
32	210620 034	6	0	1309	JG	HRD		✓
33	204530 489	2	0	1316	JG	HRD		✓
34	210 240 799	3	0	1322	JG	HRD		✓
35	204 530 394	4	0	1337	JG	HRD		✓
36	204 530 387	1	0	1349	JG	HRD		✓
37	204 350 380	2	-0.2	1356	JG	HRD		
38	204 820 125	3	0	1401	JG	HRD		
39								
40								
41								
42								
43								
44								
45								
46								
47								
48								
49								
50								

Drop Station Operator Notes

Charge $$ To Options (DO NOT USE FUNDING CODES):
AOC, NWS, HRD, NESDIS, IR/SST, AR, STAN (Stanford), SAT (JPSS/NESDIS/HRD)

AVAPS Pre-Flight Check:

- If time-permits, verify cabin pressure sensor w/ lab standard
- Start AVAPS., then start Soundings and set the Project Name and Full Flight ID (example: 20120823N2).
- Verify the Frequency band allocation as required:
  Band A: 53rd WRS - Band B: N42RF - Band C: N43RF - Band D: N49RF - Band E: Unallocated
- Select the **GPS Reference** tab from the **Soundings Displays** page and verify good GPS data
- Perform a prelaunch check on each channel, look for reasonable data and no CRC error status lights.
- Verify data is available on Remote AVAPS, then terminate the sonde.
- Verify the AVAPS Data mission folder has been created
- Verify AVAPS PC Time is correct – if time is off by >4sec, no data will display
- Early launch detects are caused usually by remanufactured sondes with the chute riser line not properly coiled below the PCB ear. This may also cause fast falls. If this is suspected, repack the riser line as time permits
- Perform RH Regeneration on all sondes – Multiple RD41 sondes may be processed at once

AVAPS Launch:

- Select a sonde frequency in the Green band and away from other sondes
- Enter sonde pressure error offset if 0.4mB or greater using cabin pressure sensor – warning, this can not be used during a climb
- If the Cal lab pressure standard and the cabin pressure standard match, apply pressure offset +/- 0.1 mB
- Wait until GPS available (green) on the pre-launch screen before continuing.
- Select "begin data collection" and verify good data with winds prior to putting sonde in launch tube
- On N42 & N43, remove about ½ of the ribbon. Do not shorten the ribbon on N49. Loosen ribbon and extend end of ribbon to near, but not over, the sensor end of the sonde. Place excess orange tape on end of ribbon to form a pocket.
- Place the sonde in the launch tube, sensor arm up, with the power pin socket facing right
- Verify the sonde is actively tracking GPS data prior to launch and no early launch detect

AVAPS Drop Log

Project: _____ Mission: HUR. LARRY Flight ID: 20210906N1

Take Off: 1545Z Landing: _____ Flt Dir: PARRISH/KALEN Launcher S/N: 02

Drop #	Sonde Serial #	Rcvr #	Press Offset	Launch Time	Operator	Charge $$ To	Comments	Good ?
1	204 820 416	1	0	1612	JG	STAN		✓
2	205 050 303	2	0	1621	JG	STAN		✓
3	204 850 495	3	0	1629	JG	STAN		✓
4	204 310 014	4	-0.3	1638	JG	STAN		✓
5	203 310 281	1	0	1647	JG	STAN		✓
6	204 820 432	2	0	1655	JG	STAN		✓
7	204 850 552	3	0	1704	JG	STAN		✓
8	203 310 604	4	0	1713	JG	STAN		✓
9	204 850 549	1	0	1717	JG	STAN		✓
10	204 820 418	5	0	1722	GD	STAN		✓
11	204 840 065	2	-0.2	1731	JG	STAN		✓
12	204 820 419	6	0	1738	GD	STAN		✓
13	204 840 673	3	0	1746	JG	STAN		✓
14	204 820 426	4	0	1755	JG	STAN		✓
15	203 210 094	1	-0.3	1807	JG	STAN		✓
16	204 460 124	2	+0.2	1813	JG	STAN		✓
17	204 840 426	3	0	1822	JG			✓
18	204 840 749	4	0	1830	GD			✓
19	204 850 529	1	0	1839				✓
20	203 240 770	2	0	1848				✓
21	205 050 297	3	0	1854				✓
22	204 650 367	4	0	1859				✓
23	204 850 518	1	0	1907				✓
24	204 850 530	5	-0.2	1915				✓
25	203 030 570	2	0	1925				✓
26	205 050 294	3	-.5	1931		HRD		✓
27	204 820 424	4	.1	1937		HRD		✓
28	204 820 410	1	.2	1943		HRD		✓
29	203 240 772	2	0	1948		HRD		✓
30	203 240 771	6	0	1955	JG	HRD		✓
31	203 320 227	3	.4	2002	JG	HRD		

1-25 STAN
26-35 HRD
Backup HRD

Drop #	Sonde Serial #	Rcvr #	Press Offset	Launch Time	Operator	Charge $$ To	Comments	Good ?
32	203 210 096	4	0	2019	JG	HRD	LOST WINDS BELOW 7500 ft.	
33	210 550 256	1	-0.2	2032	JG	HRD		
34	210 550 772	2	-0.3	2038	JG	HRD		
35	203 231 080	3	0	2044	JG	HRD		
36		4	0					
37								
38								
39								
40								
41								
42								
43								
44								
45								
46								
47								
48								
49								
50								

Drop Station Operator Notes

Charge $$ To Options (DO NOT USE FUNDING CODES):
AOC, NWS, HRD, NESDIS, IR/SST, AR, STAN (Stanford), SAT (JPSS/NESDIS/HRD)

AVAPS Pre-Flight Check:

- If time-permits, verify cabin pressure sensor w/ lab standard
- Start AVAPS., then start Soundings and set the Project Name and Full Flight ID (example: 20120823N2).
- Verify the Frequency band allocation as required:
  Band A: 53rd WRS - Band B: N42RF - Band C: N43RF - Band D: N49RF - Band E: Unallocated
- Select the **GPS Reference** tab from the **Soundings Displays** page and verify good GPS data
- Perform a prelaunch check on each channel, look for reasonable data and no CRC error status lights.
- Verify data is available on Remote AVAPS, then terminate the sonde.
- Verify the AVAPS Data mission folder has been created
- Verify AVAPS PC Time is correct – if time is off by >4sec, no data will display
- Early launch detects are caused usually by remanufactured sondes with the chute riser line not properly coiled below the PCB ear. This may also cause fast falls. If this is suspected, repack the riser line as time permits
- Perform RH Regeneration on all sondes – Multiple RD41 sondes may be processed at once

AVAPS Launch:

- Select a sonde frequency in the Green band and away from other sondes
- Enter sonde pressure error offset if 0.4mB or greater using cabin pressure sensor – warning, this can not be used during a climb
- If the Cal lab pressure standard and the cabin pressure standard match, apply pressure offset +/- 0.1 mB
- Wait until GPS available (green) on the pre-launch screen before continuing.
- Select "begin data collection" and verify good data with winds prior to putting sonde in launch tube
- On N42 & N43, remove about ½ of the ribbon. Do not shorten the ribbon on N49. Loosen ribbon and extend end of ribbon to near, but not over, the sensor end of the sonde. Place excess orange tape on end of ribbon to form a pocket.
- Place the sonde in the launch tube, sensor arm up, with the power pin socket facing right
- Verify the sonde is actively tracking GPS data prior to launch and no early launch detect

AVAPS Drop Log

Project: _____ Mission: Hur. LARRY Flight ID: 20210907N1

Take Off: 1442 Z Landing: _____ Flt Dir: DARRISA/KALOV Launcher S/N: 02

Drop #	Sonde Serial #	Rcvr #	Press Offset	Launch Time	Operator	Charge $$ To	Comments	Good ?
1	203 310 498	1	0	1545	JG	SAT		✓
2	203 350 056	2	0	1554	JG	SAT		✓
3	203 250 887	3	+0.1	1603	JG	SAT		✓
4	203 210 095	4	0	1613	JG	SAT		✓
5	203 040 055	1	+0.2	1621	JG	SAT		✓
6	203 310 060	2	0	1628	JG	SAT		✓
7	203 310 047	3	0	1637	JG	SAT		✓
8	203 310 582	4	0	1646	JG	SAT		✓
9	203 240 776	1	0	1654	JG	SAT		✓
10	203 241 005	2	+0.2	1702	JG	SAT		✓
11	203 250 851	3	0	1711	GD	SAT		✓
12	203 231 079	4	0	1718	GD	SAT		✓
13	203 320 219	1	.3	1724	GD	SAT		✓
14	203 310 048	2	-.1	1731	GD	SAT		✓
15	203 240 774	3	0	1738	GD	SAT		✓
16	203 250 867	5	0	1746	GD	SAT		✓
17	203 250 863	4	.2	1752	GD	SAT		✓
18	203 310 055	1	-.1	1758	JG	SAT		✓
19	203 240 777	2	0	1806	JG	SAT		✓
20	203 310 057	3	0	1812	JG	SAT	STOP XMT @ 2600 ft	✓
21	203 250 848	4	0	1819	JG	SAT		✓
22	203 310 494	1	-0.4	1824	JG	SAT	SLOW LAUNCH DET	✓
23	203 310 280	2	+0.3	1824	JG	SAT	BACKUP TO DROP 22	✓
24	203 031 072	5	+.2	1833	GD	SAT		✓
25	203 320 220	6	+.3	1843	GD	SAT		✓
26	203 252 853	3	+0.2	1850	JG	SAT		✓
27	203 250 864	4	0	1858	JG	SAT		✓
28	203 231 077	1	+0.2	1908	JG	SAT		✓
29	203 250 850	2	0	1920	JG	SAT	NO launch det	✗
30	203 231 090	3	0	1922	JG	SAT		
31	203 310 500	4	0	1933	JG	SAT		

32

Drop #	Sonde Serial #	Rcvr #	Press Offset	Launch Time	Operator	Charge $$ To	Comments	Good ?
32	204 530 393	5	0	1946	GD	SAT		
33	203 250 860	1	0	1958	JG	SAT		
34	210 240 502	2	-0.3	2010	JG	SAT		
35	204 530 473	3	0	2022	JG	SAT		
36								
37								
38								
39								
40								
41								
42								
43								
44								
45								
46								
47								
48								
49								
50								

Drop Station Operator Notes

Charge $$ To Options (DO NOT USE FUNDING CODES):
AOC, NWS, HRD, NESDIS, IR/SST, AR, STAN (Stanford), SAT (JPSS/NESDIS/HRD)

AVAPS Pre-Flight Check:

- If time-permits, verify cabin pressure sensor w/ lab standard
- Start AVAPS., then start Soundings and set the Project Name and Full Flight ID (example: 20120823N2).
- Verify the Frequency band allocation as required:
  Band A: 53rd WRS - Band B: N42RF - Band C: N43RF - Band D: N49RF - Band E: Unallocated
- Select the **GPS Reference** tab from the **Soundings Displays** page and verify good GPS data
- Perform a prelaunch check on each channel, look for reasonable data and no CRC error status lights.
- Verify data is available on Remote AVAPS, then terminate the sonde.
- Verify the AVAPS Data mission folder has been created
- Verify AVAPS PC Time is correct – if time is off by >4sec, no data will display
- Early launch detects are caused usually by remanufactured sondes with the chute riser line not properly coiled below the PCB ear. This may also cause fast falls. If this is suspected, repack the riser line as time permits
- Perform RH Regeneration on all sondes – Multiple RD41 sondes may be processed at once

AVAPS Launch:

- Select a sonde frequency in the Green band and away from other sondes
- Enter sonde pressure error offset if 0.4mB or greater using cabin pressure sensor – warning, this can not be used during a climb
- If the Cal lab pressure standard and the cabin pressure standard match, apply pressure offset +/- 0.1 mB
- Wait until GPS available (green) on the pre-launch screen before continuing.
- Select "begin data collection" and verify good data with winds prior to putting sonde in launch tube
- On N42 & N43, remove about ½ of the ribbon. Do not shorten the ribbon on N49. Loosen ribbon and extend end of ribbon to near, but not over, the sensor end of the sonde. Place excess orange tape on end of ribbon to form a pocket.
- Place the sonde in the launch tube, sensor arm up, with the power pin socket facing right
- Verify the sonde is actively tracking GPS data prior to launch and no early launch detect