1. Source Control Guide

Prerequisites

- Box.com Account through UPS
- Box.com Drive (https://www.box.com/resources/downloads)
- Administrator rights on the UPS laptop (for Box.com)
- Visit this link on a UPS laptop, if you do not have permissions, request them
    - https://upsinc.sharepoint.com/sites/o365-SOLDIShippingSolutionsTeam/Customer%20Document%20Management%20Library/Forms/AllItems.aspx?viewpath=%2Fsites%2Fo365-SOLDIShippingSolutionsTeam%2FCustomer%20Document%20Management%20Library%2FForms%2FAllItems.aspx&id=%2Fsites%2Fo365-SOLDIShippingSolutionsTeam%2FCustomer%20Document%20Management%20Library%2FCustomers&viewid=89107caa-acac-4e1e-bc4c-63b4272bf46f

On UPS machine:

1. Start by creating or logging into your UPS Box.com account
    a. Going to Box.com while on a UPS laptop will auto direct you to the UPS page
2. Download Box.com Drive using the link the above
    a. Log in with your UPS account
    b. In Windows Explorer, you should see a new section for Box.com
    c. Create a new folder “Projects”
    d. Add a folder under that for each client project



3. Repeat step 2 for your Blackbox laptop.
4. Repeat step 2 on any client machine where you will need to access the code.
5. The structure for uploading files will be using the standard SBR template and adding a CBR folder then putting the CBR javascript in that folder.

6. Add all necessary files from to the Box.com drive to be able to push those files up into Source Control.
7. Once on the UPS Laptop, move the files from Box.com drive to a different folder prior to trying to push to Git - it does not seem to work directly from that drive due to permission issues

Depending on the configuration of your UPS Machine, it may have a newer PSI.Sox dll. This might mean that the project will not build on your UPS Machine. If this happens, create a "References" folder in the solution and add a copy of the PSI.Sox dll from the client machine. Expand references, find PSI.Sox, and view properties to get the file path.

Setting up a Repo

Note that source control should ONLY contain code/projects. Other files will go into Sharepoint, which is detailed later.

The "DevOps - Add New Repo" document is well done. The steps that follow are more or less in that document, but they appear here to avoid going through multiple documents.

The following steps should be done on your UPS laptop while connected to the UPS VPN.

1. Navigate to tfs.ups.com/tfs/UpsProd/P01Git_CustSol_AST_Integration



2. Click the + button to the right of “P01SGit_CustSol_AST_Integration” and select “New repository” in the dropdown menu.





3. The naming convention for Repos are as follows: “CustomerName - NameOfProduct”
    a. For Booksource, it is “Booksource - SE2”
    b. NameOfProduct should be SE1 or SE2 for most of our applications, it’s the version of ShipExec that is being worked on

4. Click the Create button on the lower right of the screen.



5. Copy the URL that is generated for the repo (should be in the address bar). For example: https://tfs.ups.com/tfs/UpsProd/P01SGit_CustSol_AST_Integration/_git/Booksource%20-%20SE2



6. Open the solution in the Box drive in **Visual Studio 2019.**
7. In the lower right corner, click “Add To Source Control”.



8. Click “Git”.



9. Select the “Existing remote” option.



10. Paste the URL in the Remote URL field.



11. Click “Create and Push”.



12. If you see an error about failing to push the branch, click on the up arrow and you should be able to enter your AD information (I had to anyway, without seeing the symbol).





13. Wait until code/branch is pushed.





14. Go back to the project Git page (the copied link).
15. Click the “Create a pull request” button.



16. Enter a title (“First pull for <PROJECT>”) and any other information you want, but leave Reviewers empty (they do not have that option yet).



17. Scroll down and click “Create”.



18. On the next screen, click Approve then Complete.





19. Click “Complete Merge”.



20. Make sure that the files are there by clicking on “Files” under “Repos” on the left navigation pane.





21. Copy all files back to the Box.com drive project location.

Non-code Files

Sometimes there are files like document types (which should contain both template and control files), rate files, custom DB scripts, etc. that need to be stored. According to UPS, we should not put these items in source control.

1. Visit this link and request access if you do not already have it:
    a. https://upsinc.sharepoint.com/sites/o365-SOLDIShippingSolutionsTeam/Customer%20Document%20Management%20Library/Forms/AllItems.aspx?viewpath=%2Fsites%2Fo365-SOLDIShippingSolutionsTeam%2FCustomer%20Document%20Management%20Library%2FForms%2FAllItems.aspx&id=%2Fsites%2Fo365-SOLDIShippingSolutionsTeam%2FCustomer%20Document%20Management%20Library%2FCustomers&viewid=89107caa-acac-4e1e-bc4c-63b4272bf46f
2. Click the Sync button for this page to create a folder on your machine that will contain these files.
3. For each client, run the file “Add New Project.cmd”
    a. Enter client name
    b. Enter product
4. It’s recommended that you organize this folder with project folders for each client.
5. Move the non-code files into the client folder.

Client Cleanup

1. Uninstall Box.com Drive from client machines.
2. Make sure the latest code/files are all stored in Git/Customer Document Library.