### nixCraft

Linux / Unix tutorials for new and seasoned sysadmin || developers

→ Home

**Linux Shell Scripting Tutorial** 

RSS

Donate

Search

# Ubuntu 20.04 LTS change hostname permanently

Author: Vivek Gite

Last updated: September 7, 2020

1 comment

am a brand-new Ubuntu Linux 20.04 LTS VM user. By default, my server name to 'localhost' during cloud installation, but now I would like to change the computer name to 'ubuntu-2004-nixcraft'. Can you tell me how do I remove the localhost and set it to ubuntu-2004-nixcraft on Ubuntu 20.04 Linux? How do I change the Ubuntu computer name from 'localhost' to 'ubuntu-2004-nixcraft'? Can you tell me more about Ubuntu Linux change hostname command?



One can use the hostnamectl command to view or set the Ubuntu 20.04 LTS server's host name. The host name or computer name is usually at system startup in /etc/hostname file. Open the Terminal application and type the following commands to set or change the hostname or computer name on Ubuntu.

#### How to display the current Ubuntu hostname

Run the following command:

hostnamectl

Of course, you can use the <u>echo command/printf command</u> to print hostname too:

```
echo "$HOSTNAME"
printf "%s\n" $HOSTNAME
hostname
```

```
root@localhost ~]# hostnamectl
  Static hostname: localhost
        Icon name: computer-vm
          Chassis: vm
       Machine ID: 612892249edc4cf7b40cdfd1534feded
          Boot ID: f9ecad2978f84eaca660891d13627b4c
   Virtualization: kvm
 Operating System: Ubuntu Focal Fossa (development branch)
           Kernel: Linux 5.4.0-9-generic
     Architecture: x86-64
root@localhost ~1#
root@localhost ~]# echo "$HOSTNAME"
root@localhost ~]# printf "%s\n" $HOSTNAME
[root@localhost ~]# hostname
localhost
root@localhost ~]#
                                 © www.cyberciti.biz
```

Finally, try the <u>cat command</u> on /etc/hostname

cat /etc/hostname

#### Ubuntu 20.04 LTS change hostname permanently

The procedure to change the computer name on Ubuntu 20.04 LTS:

1. Type the hostnamectl command:

sudo hostnamectl set-hostname newNameHere
Delete the old name and setup new name.

2. Next Edit the /etc/hosts file:

```
sudo nano /etc/hosts
```

Replace any occurrence of the existing computer name with your new hostname.

3. Reboot the system to changes take effect:

sudo reboot

## How to change hostname on Ubuntu 20.04 without a system restart

Let us view current computer name setting, just type the following command:

hostnamectl

Next change hostname from localhost to ubuntu-2004-nixcraft, enter:

sudo hostnamectl set-hostname ubuntu-2004-nixcraft

Verify new changes:

hostnamectl

```
oot@localhost ~]# hostnamectl
  Static hostname: localhost
        Icon name: computer-vm
          Chassis: vm
      Machine ID: 612892249edc4cf7b40cdfd1534feded
          Boot ID: f9ecad2978f84eaca660891d13627b4c
  Virtualization: kvm
Operating System: Ubuntu Focal Fossa (development branch)
           Kernel: Linux 5.4.0-9-generic
     Architecture: x86-64
root@localhost ~]# sudo hostnamectl set-hostname ubuntu-2004-nixcraft
root@localhost ~1# hostnamectl
  Static hostname: ubuntu-2004-nixcraft
        Icon name: computer-vm
          Chassis: vm
      Machine ID: 612892249edc4cf7b40cdfd1534feded
          Boot ID: f9ecad2978f84eaca660891d13627b4c
  Virtualization: kvm
Operating System: Ubuntu Focal Fossa (development branch)
           Kernel: Linux 5.4.0-9-generic
Architecture: x86-64
root@localhost ~]#
                                            © www.cyberciti.biz
```

Find your public or private IP address by running the <u>ip command</u>:

```
ip a
ip a s eth0
```

```
12: eth0@if13: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc noqueue state UP group default qlen 1000 link/ether 00:16:3e:24:b3:08 brd ff:ff:ff:ff:ff:ff link-netnsid 0 inet 10.105.28.43/24 brd 10.105.28.255 scope global eth0 valid_lft forever preferred_lft forever inet6 fe80::216:3eff:fe24:b308/64 scope link valid_lft forever preferred_lft forever
```

Update /etc/hosts file with that IP address such as 10.105.28.43 using a text editor such as vim command/nano command:

```
$ sudo vi /etc/hosts
```

OR

\$ sudo nano /etc/hosts

Update/append:

```
10.105.28.43 ubuntu-2004-nixcraft
```

Make sure you replace all occurrence of the old computer name with your new one too. <u>Save and</u> close the file in vim.

#### Conclusion

You learned how to change hostname permanently when using Ubuntu 20.04 LTS server or desktop computer as per your project needs.

This entry is **17** of **19** in the **Linux/Unix Set hostname Tutorial** series. Keep reading the rest of the series:

- 1. <u>Ubuntu Linux Change Hostname (computer name)</u>
- 2. <u>Debian Linux: Change Hostname / Computer Name Permanently</u>
- 3. <u>Linux change my hostname / computer system name</u>
- 4. Linux Change Hostname
- 5. RHEL / Centos Linux 7: Change and Set Hostname Command
- 6. OpenBSD Change Hostname
- 7. CentOS Linux 5/6 Change Hostname Command
- 8. Linux setting hostname and domain name of my server
- 9. FreeBSD Change Hostname without reboot
- 10. SuSe Linux Change Hostname without reboot
- 11. How to set the hostname on Fedora Linux
- 12. <u>Ubuntu 18.04 LTS change hostname permanently</u>
- 13. <u>Ubuntu set hostname permanently (computer name) command</u>
- 14. OpenSUSE Linux set hostname permanently (computer name) command
- 15. RHEL 8 Linux set hostname permanently (computer name) command
- 16. CentOS 8 Linux set hostname permanently (computer name) command
- 17. Ubuntu 20.04 LTS set hostname permanently (computer name) command
- 18. Set / Change FQDN on Ubuntu 20.04 LTS
- 19. Alpine Linux Setting system hostname
- If you liked this page, please support my work on <u>Patreon</u> or with a <u>donation</u>.
- Get the latest tutorials on SysAdmin, Linux/Unix, Open Source/DevOps topics:
  - RSS feed or Weekly email newsletter

• Share on <u>Twitter</u> • <u>Facebook</u> • 1 comment... <u>add one</u> ↓

#### **UP NEXT**



How to install KVM on Ubuntu 20.04 LTS Headless Server



cat command in Linux / Unix with Examples



How to install KVM on CentOS 8 Headless Server



How to install and setup LXC (Linux Container) on Fedora Linux 26

Ubuntu 18.04 LTS change hostname permanently

Installing kvm on Ubuntu Linux using apt-get

How to Change Hostname on Ubuntu 20.04

Category	List of Unix and Linux commands
File Management	cat
Firewall	Alpine Awall • CentOS 8 • OpenSUSE • RHEL 8 • Ubuntu 16.04 • Ubuntu 18.04 • Ubuntu 20.04
Network Utilities	dig • host • ip • nmap

Category	List of Unix and Linux commands
OpenVPN	CentOS 7 • CentOS 8 • Debian 10 • Debian 8/9 • Ubuntu 18.04 • Ubuntu 20.04
Package Manager	apk • apt
Processes Management	bg • chroot • cron • disown • fg • jobs • killall • kill • pidof • pstree • pwdx • time
Searching	grep • whereis • which
User Information	<u>groups • id • lastcomm • last • lid/libuser-lid • logname • members • users • whoami • who • w</u>
WireGuard VPN	Alpine • CentOS 8 • Debian 10 • Firewall • Ubuntu 20.04

#### Comments on this entry are closed.

#### Vivek Gite

Jan 22, 2020 @ 18:28

Still, got a problem setting up hostname on an Ubuntu 20.04 LTS box? Post <u>your question on the</u> nixcraft forum thread here.

link

Use HTML ,..., <code>...</code> and <kbd>...</kbd> for code samples.

Next FAQ: Explain DEBIAN\_FRONTEND apt-get variable for Ubuntu / Debian

Previous FAQ: <u>Upgrade Ubuntu 18.04 to 20.04 LTS using command line</u>

#### **Featured Articles**

1

30 Cool Open Source Software I Discovered in 2013

3	Top 32 Nmap Command Examples For Linux Sys/Network Admins
4	25 PHP Security Best Practices For Linux Sys Admins
5	30 Linux System Monitoring Tools Every SysAdmin Should Know
6	40 Linux Server Hardening Security Tips
7	Linux: 25 Iptables Netfilter Firewall Examples For New SysAdmins
8	Top 20 OpenSSH Server Best Security Practices
9	Top 25 Nginx Web Server Best Security Practices
10	My 10 UNIX Command Line Mistakes

30 Handy Bash Shell Aliases For Linux / Unix / Mac OS X