

```
*Jul 13 12:49:20.650: %LINK-3-UPDOWN: Interface Ethernet0/1, changed state to do
wn
*Jul 13 12:49:20.658: %LINK-3-UPDOWN: Interface Ethernet0/2, changed state to do
wn
*Jul 13 12:49:20.663: %LINK-3-UPDOWN: Interface Ethernet0/3, changed state to do
wn
*Jul 13 12:49:21.650: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/
1, changed state to down
*Jul 13 12:49:21.658: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/
2, changed state to down
*Jul 13 12:49:21.663: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/
3, changed state to down
ROUTER#
ROUTER#conf ter
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#interface ethernet 0/0
ROUTER(config-if)#ip address 50.0.0.20 255.0.0.0
ROUTER(config-if)#no shutdown
ROUTER(config-if)#line console 0
ROUTER(config-line)#username sujith password sujith
ROUTER(config)#login
% Incomplete command.

ROUTER(config)#username sujith password sujith
ROUTER(config)#line console 0
ROUTER(config-line)#login local
ROUTER(config-line)#exit
ROUTER(config)#line vty 0 4
ROUTER(config-line)#transport input telnet
ROUTER(config-line)#login local
ROUTER(config-line)#exit
ROUTER(config)#enable secret sujith
ROUTER(config)#exit
ROUTER#
*Jul 13 12:53:10.239: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#
```

ROUTER con0 is now available

Press RETURN to get started.

User Access Verification

Username: sujith

Password:


ROUTER>en

Password:

ROUTER#show ip interface brief

Interface	IP-Address	OK?	Method	Status	Protocol
Ethernet0/0	50.0.0.20	YES	manual	up	up
Ethernet0/1	unassigned	YES	TFTP	down	down
Ethernet0/2	unassigned	YES	TFTP	down	down
Ethernet0/3	unassigned	YES	TFTP	down	down

ROUTER#



50.0.0.20 - PuTTY

User Access Verification

Username: █

1:03 PM

User Access Verification

Username: sujith

Password:

ROUTER>en

Password:

ROUTER#show ip interface brief

Interface	IP-Address	OK?	Method	Status	Protocol
Ethernet0/0	50.0.0.20	YES	manual	up	up
Ethernet0/1	unassigned	YES	TFTP	down	down
Ethernet0/2	unassigned	YES	TFTP	down	down
Ethernet0/3	unassigned	YES	TFTP	down	down

ROUTER#show route

```
ROUTER#show ip route
```

```
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
```

```
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
```

```
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
```

```
E1 - OSPF external type 1, E2 - OSPF external type 2
```

```
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
```

```
ia - IS-IS inter area, * - candidate default, U - per-user static route
```

```
o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
```

```
a - application route
```

```
+ - replicated route, % - next hop override
```

```
Gateway of last resort is not set
```

```
50.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
```

```
C      50.0.0.0/8 is directly connected, Ethernet0/0
```

```
L      50.0.0.20/32 is directly connected, Ethernet0/0
```

```
ROUTER#
```