

FortiClient VPN Installation Guide for Windows

Windows Installation and Configuration Manual
Central Computer and Informatics Centre (CIC)
Indian Institute of Technology Kharagpur

This guide explains how to install FortiClient VPN, configure the IIT Kharagpur SSL-VPN connection, connect securely, and disconnect after use.

Before you begin: Download the FortiClient installer recommended by CIC and keep the VPN username and password issued to you by CIC ready.

VPN Installation

Step 1: Start the FortiClient installer.


Double-click the downloaded installer. Read and accept the licence agreement, and then continue to the next screen.



Screenshot 1

Step 2: Select Secure Remote Access.


On the setup-type screen, select **Secure Remote Access**, and then click **Next**.



Screenshot 2

Step 3: Install FortiClient.

Click **Install** to begin. Follow the on-screen instructions until the installation is complete.




Screenshot 3

VPN Configuration

Step 1: Open the VPN configuration screen.

After installation, open FortiClient. Select **Remote Access**, and then click **Configure VPN**.



Screenshot 4

Step 2: Configure the SSL-VPN connection.

Enter the connection details as follows:

- Select **SSL-VPN**.
- Enter a suitable name in **Connection Name**.
- Set **Remote Gateway** to **vpn.iitkgp.ac.in/iit**, or use the gateway address specifically provided by CIC.
- Click **Save**.

The screenshot shows the FortiClient application window with the 'New VPN Connection' dialog box open. The left sidebar contains navigation options: IIT, COMPLIANCE & TELEMETRY, VULNERABILITY SCAN, REMOTE ACCESS (highlighted), Notifications, Settings, and About. At the bottom of the sidebar is an 'Unlock Settings' button. The main area of the dialog is titled 'New VPN Connection' and has two tabs: 'SSL-VPN' (selected) and 'IPsec VPN'. The 'SSL-VPN' tab contains the following fields and options:

- VPN:** Two tabs, 'SSL-VPN' and 'IPsec VPN'. 'SSL-VPN' is selected.
- Connection Name:** A text box containing 'iitkgp'.
- Description:** An empty text box.
- Remote Gateway:** A text box containing 'vpn.iitkgp.ac.in/iit'. Below it is a '+Add Remote Gateway' button.
- Customize port:** A checkbox that is unchecked, followed by a text box containing '443'.
- Client Certificate:** A dropdown menu showing 'None'.
- Authentication:** Three radio buttons: 'Prompt on login' (selected), 'Save login', and 'Do not Warn Invalid Server Certificate' (unchecked).


At the bottom of the dialog are two buttons: 'Cancel' and 'Save'.

Screenshot 5

Connect to the VPN

Step 1: Sign in to the configured VPN connection.


- Select **Remote Access** again.
- Choose the VPN connection you configured from the drop-down list.
- Enter the username and password provided by CIC, and click **Connect**.



Screenshot 6

Step 2: Confirm that the VPN is connected.

When the connection succeeds, the **VPN Connected** screen appears. You may minimize FortiClient and begin working.



Screenshot 7

Disconnect

When your work is complete, return to FortiClient and click **Disconnect** on the VPN Connected screen.

For further assistance, email helpdesk@cc.iitkgp.ac.in.