

ABAQUS 6.14 Installation Guide

Windows Installation Manual
Central Computer & Informatics Centre (CIC)
Indian Institute of Technology Kharagpur

This document provides detailed step-by-step instructions for installing **ABAQUS 6.14** on Microsoft Windows systems using the CIC Software Repository.

Important Note: For the latest version of ABAQUS, please check the CIC software repository at <http://swrepo.iitkgp.ac.in>.

Step 1: Click Run [\\swrepo.iitkgp.ac.in] to login to the software repository.


Step 2: Login using Username / Password: guest.

Step 3: Open the Software Repository.


Step 4: Navigate to the folder Abaqus-6.14-allOS.

Step 5: Copy all installation contents locally to your machine.


Step 6: Extract all contents of the Document folder one by one before installing ABAQUS.




Step 7: Double click Doc_SIMULIA_Abaqus.ALLOS.




Step 8: Open Directory 1.







Step 9: Run setup.exe.





Step 10: Click Next to continue.









Step 11: Click OK when prompted.




Step 12: Click Install to begin documentation installation.




Step 13: Wait for the installation to complete.








Step 14: Extract the Abaqus software packages sequentially (1.4, 2.4, 3.4, 4.4).





Step 15: Double click SIM_Abaqus.ALLOS.





Step 16: Open Directory 1 and run setup.exe.



Step 17: Continue through the setup wizard using Next and Continue.





Abaqus 6.14 Product Installer

License server

☒ License Notice
☒ Introduction
☒ Installation Help
☒ Installation type
☒ License server
☐ Documentation
☐ Installation directory
☐ Abaqus working directory
☐ Pre-installation summary
☐ Installing...
☐ Product verification results
☐ Installation complete

InstallAnywhere by Macrovision

Cancel Previous Next

Please enter the hostname or IP address of your Abaqus license server(s). Include the port if your server is on a non-default port.

FLEXnet examples: 27000@maroon.abaqus.com or rose.abaqus.com

DSLS example: crimson:4085

License server 1 (REQUIRED)

abqs.iitkgp.ac.in

Redundant license servers (optional)

Server 2

Server 3

Abaqus 6.14 Product Installer

Documentation

☒ License Notice
☒ Introduction
☒ Installation Help
☒ Installation type
☒ License server
☒ Documentation
☐ Installation directory
☐ Abaqus working directory
☐ Pre-installation summary
☐ Installing...
☐ Product verification results
☐ Installation complete

InstallAnywhere by Macrovision

Cancel Previous Next

Please enter the URL for Abaqus HTML documentation or the base installation directory for Abaqus PDF documentation. If documentation has not been installed please leave this field blank.

Searchable HTML Format:
 http://<computername>:<port_number>/v6.14
 Example: http://cassidy.simulia.com:2080/v6.14

Non-searchable HTML format:
 file:///<installation_dir>/Documentation/docs/v6.14/index.html
 Example: file:///d:/abaqus/Documentation/docs/v6.14/index.html

PDF Format:

**Undefined documentation URL**

Abaqus products access the Abaqus documentation using a URL that is defined at the conclusion of the documentation installation. By making note of this URL and supplying it here, the product installation procedure configures Abaqus with this information. If, however, you install Abaqus products without supplying this URL, you must manually configure your product installation after you install documentation. For this reason, it is strongly recommended that Abaqus documentation be installed before Abaqus products.



If you already installed documentation, please enter the URL that was given to you at the conclusion of that installation. The URL is included in the file


Documentation/installation_info/v6.14/info.log

of the documentation installation.


If you have not installed documentation, it is recommended that you do so before proceeding.

Click "Previous" to enter your Abaqus documentation URL.
Click "Continue" to proceed without specifying a URL.
Click "Quit" to exit the installation.









Step 18: Click Install to begin software installation.



Step 19: Wait for installation to complete.





Step 20: Click Next / Finish to complete setup.

Step 21: Installation completed successfully.

End of Document