

ANSYS Lumerical 2025 R2 Installation Guide

Windows Installation Manual
Central Computer & Informatics Centre (CIC)
Indian Institute of Technology Kharagpur

This document provides step-by-step instructions for installing **ANSYS Lumerical 2025 R2** on Windows systems using the CIC Software Repository. All screenshots from the provided archive have been included and placed with their corresponding installation steps.

Important Note: For the latest version of ANSYS, check the CIC software repository at <http://swrepo.iitkgp.ac.in>.

Installation Procedure


Step 1: Run `\\swrepo.iitkgp.ac.in` to log in to the software repository. Login ID / Password: `guest`.

Step 2: Go to the Software Repository.

Step 3: Go to the folder `Ansyz2025R2`.


Step 4: Go to the folder `Win` and download the required ANSYS module ZIP package. For Lumerical, download `LUMERICAL_2025R2.04_WINX64.zip`.

Step 5: Extract the package to the `LUMERICAL_2025R2.04_WINX64` folder.




Screenshot 1

Step 6: Go to the `LUMERICAL_2025R2.04_WINX64\Lumerical_Suite` folder, right-click on `Lumerical_Installer` and click `Run as administrator`.




Screenshot 2

Step 7: Click Install.




Screenshot 3

Step 8: Click Next.




Screenshot 4

Step 9: Check the Terms and Conditions option and click Next.




Screenshot 5

Step 10: Click Next.




Screenshot 6

Step 11: Click Install.




Screenshot 7

Step 12: Installation will start.




Screenshot 8

Step 13: Installation is in progress.




Screenshot 9

Step 14: Click Finish.




Screenshot 10

Step 15: Go to the Windows Start Menu, open the Ansys Optics 2025 R2.4 directory, and click Ansys Optics Launcher 2025 R2.4.




Screenshot 11

Step 16: After Ansys Optics Launcher opens, click *I have a license from Ansys already*.




Screenshot 12

Step 17: Click *I want to configure my license only for Lumerical products*.




Screenshot 13

Step 18: Click Go to Licensing Setup.




Screenshot 14

Step 19: Click Open Ansys Client Settings.



Screenshot 15

Step 20: Ansys Licensing Settings will open.




Screenshot 16

Step 21: Enable licensing by clicking the Enabled toggle. Fill in the following license details, then click Test and after successful testing click Save:

Port: 1055


Server1: ansys.iitkgp.ac.in.



Screenshot 17


Step 22: Close the Licensing Settings 2025 R2 application and return to the already opened Ansys Optics Launcher.

Step 23: Click Use Ansys Client Settings, then click Apply.




Screenshot 18

Step 24: Click Restart Now.



Screenshot 19

Step 25: Ansys Optics Launcher will reopen and the installation will be completed successfully.



Screenshot 20

Post-Installation Note

After installation and license configuration are complete, relaunch ANSYS Optics Launcher and verify that the Lumerical environment starts correctly.

End of Document