- 1. 64725 порт TCP ESTABLISHED firefox.exe Console Процесс firefox
- 2. 27017 порт TCP LISTENING mongod.exe Services Процесс MongoDb
- 3. 33060 порт TCP LISTENING mysqld.exe Services Процесс MySql
- 4. 9990 порт TCP LISTENING VideohubServer.exe Services Видео сервер
- 5. 53108 порт TCP ESTABLISHED devenv.exe Console Процесс Microsoft Visual Studio
- 6. 9990 порт UDP VideohubServer.exe Services Видео сервер
- 7. 123 порт UDP svchost.exe Services Системный процесс для загрузки служб
- 8. 53108 порт UDP devenv.exe Console Процесс Microsoft Visual Studio
- 9. 10884 порт UDP RuntimeBroker.exe Console Системный процесс
- 10. 445 порт loc-srv Удаленный вызов процедур

При одном подключении по ssh к серверу с Ubuntu:

```
Proto Recv-Q Send-Q Local Address
                                               Foreign Address
                                                                         State
tcp
           0
                   0 0.0.0.0:80
                                               0.0.0.0:*
                                                                         LISTEN
tcp
           0
                   0 127.0.0.53:53
                                               0.0.0.0:*
                                                                         LISTEN
tcp
           0
                   0 0.0.0.0:22
                                               0.0.0.0:*
                                                                         LISTEN
           0
                   0 127.0.0.1:631
                                               0.0.0.0:*
                                                                         LISTEN
tcp
                   0 127.0.0.1:6010
           0
                                               0.0.0.0:*
                                                                         LISTEN
tcp
                   0 172.31.44.209:22
                                               62.213.98.170:49292
           0
                                                                         ESTABLISHED
tcp
                                               62.213.98.170:49290
           0
                 240 172.31.44.209:22
                                                                         ESTABLISHED
tcp
           0
                   0
                     :::80
tcp6
                                                                         LISTEN
           0
                   0
                     :::22
tcp6
                                                                         LISTEN
           0
                     ::1:631
tcp6
                   0
                                                                         LISTEN
tcp6
                   Θ
                     ::1:6010
                                                                         LISTEN
```

При двух подключениях по ssh к серверу с Ubuntu:

```
Active Internet connections (servers and established)
roto Recv-Q Send-Q Local Address
                                              Foreign Address
                                                                        State
           0
                  0 0.0.0.0:80
                                              0.0.0.0:*
                                                                        LISTEN
cp
           0
                  0 127.0.0.53:53
                                              0.0.0.0:*
                                                                        LISTEN
ср
           Θ
                  0 0.0.0.0:22
                                              0.0.0.0:*
                                                                        LISTEN
ср
           Θ
                  0 127.0.0.1:631
                                              0.0.0.0:*
                                                                        LISTEN
ср
                  0 127.0.0.1:6010
           0
                                              0.0.0.0:*
                                                                        LISTEN
ср
           0
                  0 127.0.0.1:6011
                                              0.0.0.0:*
                                                                        LISTEN
ср
           0
                  0 172.31.44.209:22
                                              62.213.98.170:49292
                                                                        ESTABLISHED
ср
           0
                  0 172.31.44.209:22
                                              62.213.98.170:49402
                                                                        ESTABLISHED
ср
           0
                  0 172.31.44.209:22
                                              62.213.98.170:49403
                                                                        ESTABLISHED
ср
           0
                240 172.31.44.209:22
                                              62.213.98.170:49290
                                                                        ESTABLISHED
ср
cp6
           0
                  0 :::80
                                              :::*
                                                                        LISTEN
cp6
           0
                  0 :::22
                                              :::*
                                                                        LISTEN
cp6
           0
                  0 ::1:631
                                                                        LISTEN
cp6
           0
                  0 ::1:6010
                                              :::*
                                                                        LISTEN
cp6
           0
                  0 ::1:6011
                                              :::*
                                                                        LISTEN
```

При трех подключениях по ssh к серверу с Ubuntu:

Active Internet connections (servers and established)					
Proto	Recv-Q	Send-Q	Local Address	Foreign Address	State
tcp	Θ	Θ	0.0.0.0:80	0.0.0.0:*	LISTEN
tcp	Θ	Θ	127.0.0.53:53	0.0.0.0:*	LISTEN
tcp	Θ	Θ	0.0.0.0:22	0.0.0.0:*	LISTEN
tcp	Θ	Θ	127.0.0.1:631	0.0.0.0:*	LISTEN
tcp	Θ	Θ	127.0.0.1:6010	0.0.0.0:*	LISTEN
tcp	Θ	Θ	127.0.0.1:6011	0.0.0.0:*	LISTEN
tcp	Θ	Θ	127.0.0.1:6012	0.0.0.0:*	LISTEN
tcp	Θ	Θ	172.31.44.209:22	62.213.98.170:49408	ESTABLISHED
tcp	Θ	Θ	172.31.44.209:22	62.213.98.170:49292	ESTABLISHED
tcp	Θ	Θ	172.31.44.209:22	62.213.98.170:49402	ESTABLISHED
tcp	Θ	Θ	172.31.44.209:22	62.213.98.170:49403	ESTABLISHED
tcp	Θ	Θ	172.31.44.209:22	62.213.98.170:49409	ESTABLISHED
tcp	Θ	240	172.31.44.209:22	62.213.98.170:49290	ESTABLISHED
tcp6	Θ	Θ	:::80	:::*	LISTEN
tcp6	Θ	Θ	:::22	:::*	LISTEN
tcp6	Θ	Θ	::1:631	:::*	LISTEN
tcp6	Θ	Θ	::1:6010	:::*	LISTEN
tcp6	Θ	Θ	::1:6011	:::*	LISTEN
tcp6	Θ	Θ	::1:6012	:::*	LISTEN

Можно сделать вывод, что на каждое подключение устанавливается по два процесса.