Cisco AnyConnect Profile:






AnyConnect Profile Editor - Network Access Manager
File Help
Network Access Manager
Client Policy
Authentication Policy
Networks
Network Groups
Networks
Profile: Untitled
Network Connection Type
Machine Connection
This should be used if the end station should log onto the network before the user logs in. This is typically used for connecting to domains, to get GPO's and other updates from the network before the user has access.
User Connection
The user connection should be used when a machine connection is not needed. A user connection will make the network available after the user has logged on.
Machine and User Connection
This type of connection will be made automatically when the machine boots. It will then be brought down, and back up again with different credentials when the user logs in.
Media Type
Security Level
Connection Type
Machine Auth
Credentials
User Auth
Credentials
Next
Cancel


AnyConnect Profile Editor - Network Access Manager
File Help
Network Access Manager
Client Policy
Authentication Policy
Networks
Network Groups
Networks
Profile: Untitled
EAP Methods
EAP-TLS
PEAP
EAP-TTLS
EAP-FAST
LEAP
EAP-PEAP Settings
Validate Server Identity
Enable Fast Reconnect
Inner Methods based on Credentials Source
Authenticate using a Password
EAP-MSCHAPv2
EAP-GTC
EAP-TLS, using a Certificate
Media Type
Security Level
Connection Type
Machine Auth
Credentials
User Auth
Credentials
Next
Cancel


AnyConnect Profile Editor - Network Access Manager
File Help
Network Access Manager
Client Policy
Authentication Policy
Networks
Network Groups
Networks
Profile: Untitled
Machine Identity
Unprotected Identity Pattern:
host/anonymous
Protected Identity Pattern:
host/[username]
Machine Credentials
Use Machine Credentials
Use Static Credentials
Password:
Media Type
Security Level
Connection Type
Machine Auth
Credentials
User Auth
Credentials


AnyConnect Profile Editor - Network Access Manager
File Help
Network Access Manager
Client Policy
Authentication Policy
Networks
Network Groups
Networks
Profile: Untitled
EAP Methods
EAP-TLS
PEAP
EAP-TTLS
EAP-FAST
LEAP
Extend user connection beyond log off
EAP-PEAP Settings
Validate Server Identity
Enable Fast Reconnect
Disable when using a Smart Card
Inner Methods based on Credentials Source
Authenticate using a Password
EAP-MSCHAPv2
EAP-GTC
EAP-TLS, using a Certificate
Authenticate using a Token and EAP-GTC
Media Type
Security Level
Connection Type
Machine Auth
Credentials
User Auth
Credentials


AnyConnect Profile Editor - Network Access Manager
File Help
Network Access Manager
Client Policy
Authentication Policy
Networks
Network Groups
Networks
Profile: Untitled
User Identity
Unprotected Identity Pattern:
anonymous
Protected Identity Pattern:
[username]
User Credentials
Use Single Sign On Credentials
Prompt for Credentials
Remember Forever
Remember while User is Logged On
Never Remember
Use Static Credentials
Password:
Media Type
Security Level
Connection Type
Machine Auth
Credentials
User Auth
Credentials
Done
Cancel


AnyConnect Profile Editor - Network Access Manager
File Help
Save
Save in:
Desktop
Recent Items
Desktop
My Docum...
Computer
Network
Libraries
Admin
Computer
Network
MobaXterm
abc.txt
Xiao Stenography
File name:
Wireless-Config.xml
Files of type:
All Files
Save
Cancel