ERC721AOwnable

About

Style: 2-3 lines description

Content: What issue does this module solve?

ERC721 Non Fungible Token Standard with gas optimization when minting many NFTs at the same time.

Tags

5-7 keywords about the contract which will later be used for search. Content: use-case in the biz term, technical traits

- token
- ERC721
- NFT
- NFT Sale

Features

Style: bullet points

Content: Who-How-What

"There is no any ready-to-use feature to mention here as it is."

- V NFT sale with an configurable price.
- Reserve function for the contract owner to mint free NFTs.
- V Fixed maximum supply.
- Reduced gas costs when minting NFTs at the same time.
 - once ERC721ABase.sol properly inherits ERC721A, then this feature will be included.

How To Use

Before Deployment

- 1. Owner will decide following NFT features before starting NFT sale.
- baseURI
- price: price to sell each NFT for investors
- maxSupply: The max amount of NFTs |default 10000
- maxMintQuantity: the max quantity for one investor to mint NFTs|default 3
- startTokenId: tokenId to start counting minted NFTs|usually 0

Deployment


1. Deploy this contract though Bunzz application deploy button.


2. Input the following module parameters when deployment. name, symbol, startTokenId, baseURI, price, maxSupply`

Operation to sell NFTs

- 1. Make sure each configuration is correct. If not, you can update by following functions.
- setBaseURI()
- setCurrentPrice()
- setMaxSupply()
- 2. anyone can mint up to the maximum amount of token by mint() function.
- 3. Only Owner can mint any arbitrary amount of NFTs from ownerMint() function.
- 4. After the NFT sale is finished, only owner can withdraw the ethereum stored on contact by withdraw() function.

Operation Diagram





Module Parameters

ERC721AOwnable

ERC721 contract which the following features

- NFT sale with an configurable price.
- Reserve function for the contract owner to mint free NFTs.
- Fixed maximum supply.

constructor(string name_, string symbol_, uint256 startTokenId_, string baseURI_, uint256 price, uint256 maxSupply_) public

Parameters

Name	Type	Description	
name_	string	NFT Name	
symbol_	string	NFT Symbol	
startTokenId_	uint256	the starting number of tokenId	
baseURI_	string	basement of URI concatinating with tokenId	
price	uint256	the price to sale NFT in Ethereum	
maxSupply_	uint256	the maximum supply of all NFTs	

Function

WRITE

mint

function mint(uint256 quantity) public payable

anyone can mint the quantity of NFT up to maxMintQuantity. Requirements:

- the max mintable qunatitiy for one user is maxMintQuantity.
- total quantity of NFT will not be exceed the maxSupply.
- sender should pay the exact amount of price * quantity.

Parameters

Name	Type	Description	
quantity	uint256	the quantity of minting NFT	

ownerMint

function ownerMint(address to, uint256 quantity) public

only contact owner can mint a quantity of NFT for free. Requirements:

• total quantity of NFT will not be exceed the maxSupply.

Parameters

Name	е Туре	Description
to	address	the receiver's wallet address
quant	tity uint256	the quantity of minting NFT

Parameters

Name	Type	Description
to	address	the receiver address
guantity	uint256	the quantity of minting NFT

burn

function burn(uint256 tokenId) public virtual

Only contact owner can burn the NFT token by specifing the tokenId.

Parameters

Name	Туре	Description	
tokenId	uint256	the tokenId of NFT	

withdraw

function withdraw() external

A way for the owner to withdraw all proceeds from the sale.

setBaseURI

function setBaseURI(string baseURI_) public

Updates the baseURI that will be used to retrieve NFT metadata.

Parameters

Name	Type	Description	
baseURI	strina	The baseURI to be used.	

Return Values

Name	Type	Description
[0]	string	(string memory) Base URI

setMaxSupply

function setMaxSupply(uint256 _maxSupply) public

Only contract owner can update the total supply of NFTs.

Parameters

Name	Туре	Description
_maxSupply	uint256	the quantity of total amount

setCurrentPrice

function setCurrentPrice(uint256 price) external

Sets the price of each NFT during the initial sale.

Parameters

Name	Type	Description
price	uint256	The price of each NFT during the initial sale

setMaxMintQuantity

function setMaxMintQuantity(uint256 _maxMintQuantity) public

Only contract owner can update the maximum quantity for one user to mint NFT. The default is 3 for one wallet address.

Parameters

Name	Туре	Description
_maxMintQuantity	uint256	the maximum quantity of NFTs

approve

function approve(address to, uint256 tokenId) public

See {IERC721-approve}.

setApprovalForAll

function setApprovalForAll(address operator, bool approved) public virtual

See {IERC721-setApprovalForAll}.

transferFrom

function transferFrom(address from, address to, uint256 tokenId) public virtual

See {IERC721-transferFrom}.

safeTransferFrom

function safeTransferFrom(address from, address to, uint256 tokenId)
public virtual

See {IERC721-safeTransferFrom}.

READ

numberMinted

function numberMinted(address owner) public view returns (uint256)

return the number of NFT which the owner has minted so far.

Parameters

Name	Туре	Description
owner	address	the address of NFT owner

Return Values

Name	Type	Description
------	------	-------------

Name	Type	Description	
[0]	uint256	numberMinted	

numberBurned

function numberBurned(address owner) public view returns (uint256)

return the number of NFT which the owner has burned so far.

Parameters

_	Name	Туре	Description
	owner	address	the address of NFT owner

Return Values

Name	Type	Description	
[0]	uint256	numberBurned	

getApproved

function getApproved(uint256 tokenId) public view returns (address)

See {IERC721-getApproved}.

name

function name() public view virtual returns (string)

See {IERC721Metadata-name}.

symbol

function symbol() public view virtual returns (string)

See {IERC721Metadata-symbol}.

tokenURI

function tokenURI(uint256 tokenId) public view virtual returns (string)

See {IERC721Metadata-tokenURI}.

balanceOf

function balanceOf(address owner) public view returns (uint256)

See {IERC721-balanceOf}.

ownerOf

function ownerOf(uint256 tokenId) public view returns (address)

See {IERC721-ownerOf}.

baseURI

function baseURI() public view returns (string)

getter of _baseURI

Return Values

Name	Type	Description	
[0]	string	_baseURI	

exists

function exists(uint256 tokenId) public view returns (bool)

check if the tokenId exists or not.

Parameters

Name	Type	Description
tokenId	uint256	the tokenId of NFT

Return Values

Name	Type	Description
[0]	bool	boolean

startTokenId

function startTokenId() public view returns (uint256)

To change the starting tokenId, please override this function.

Return Values

Name	Type	Description
[0]	uint256	(uint256) Start Token ID

totalSupply

function totalSupply() public view returns (uint256)

Burned tokens are calculated here, use <u>_totalMinted()</u> if you want to count just minted tokens.

Return Values

Name	Type	Description
[0]	uint256	(uint256) Total supply

supportsInterface

function supportsInterface(bytes4 interfaceId) public view virtual returns
(bool)

See {IERC165-supportsInterface}.

isApprovedForAll

function isApprovedForAll(address owner, address operator) public view virtual returns (bool)

See {IERC721-isApprovedForAll}.

totalMinted

function totalMinted() public view returns (uint256)

return the number of all minted tokens without considering burned tokens.

Event

Transfer

Emitted when tokenId token is transferred from from to to.

event Transfer(address indexed from, address indexed to, uint256 indexed tokenId);

Approval

Emitted when owner enables approved to manage the tokenId token.

event Approval(address indexed owner, address indexed approved, uint256
indexed tokenId);

ApprovalForAll

Emitted when owner enables or disables (approved) operator to manage all of its assets.

event ApprovalForAll(address indexed owner, address indexed operator, bool approved);

OwnershipTransferred