```
[root@swapnil ~]# free -h
              total
                          used
                                      free
                                                 shared
                                                         buff/cache
                                                                      available
Mem:
              3.5Gi
                          1.4Gi
                                      1.8Gi
                                                   23Mi
                                                              686Mi
                                                                          2.2G
Swap:
              2.0Gi
                             0B
                                      2.0Gi
[root@swapnil ~]# fallocate -l 1G /swapfile
[root@swapnil ~]# chmod 600 /swapfile
[root@swapnil ~]# mkswap /swapfile
Setting up swapspace version 1, size = 1024 MiB (1073737728 bytes)
no label, UUID=85e53c31-bf10-40bd-8b88-64f9e17198c5
[root@swapnil ~]# swapon /swapfile
[root@swapnil ~]# swapon --show
               SIZE USED PRIO
NAME
         TYPE
/dev/dm-1 partition
                      2G
                           0B
                                -2
/swapfile file
                   1024M
                           0B
                              -3
[root@swapnil ~]# free -h
                                                                      available
              total
                        used
                                      free
                                                 shared
                                                         buff/cache
                                                   23Mi
Mem:
                          1.4Gi
                                     1.8Gi
                                                              687Mi
              3.5Gi
                                                                          2.2G
              3.0Gi
                             0B
                                      3.0Gi
Swap:
[root@swapnil ~]# echo '/swapfile none swap sw 0 0' | sudo tee -a /etc/fstab
/swapfile none swap sw 0 0
```

```
root@swapnil ~|# cat /etc/fstab
 /etc/fstab
 Created by anaconda on Wed Sep 25 16:56:50 2024
 Accessible filesystems, by reference, are maintained under '/dev/disk/'.
 See man pages fstab(5), findfs(8), mount(8) and/or blkid(8) for more info.
 After editing this file, run 'systemctl daemon-reload' to update systemd
 units generated from this file.
/dev/mapper/rhel-root /
                                                        defaults
                                                xfs
                                                                        0 0
UUID=ae0479c4-29af-4090-a23b-a0ad02b62f2d /boot
                                                                          defaul
                                                                  xfs
ts
          0 0
UUID=0CC6-B8D4
                        /boot/efi
                                                vfat
                                                        umask=0077, shortname=win ise L
nt 0 2
/dev/mapper/rhel-swap
                                                        defaults
                                                                        0 0
                        none
                                                swap
/swapfile none swap sw 0 0
```