

Input Code Reference

What each short code in the EA input panel means, and how it affects risk.

Code	Setting	What it means	If you increase it
D1	Entry Distance	How far from current price the EA places its first orders.	Fewer, later entries
V1	Starting Lot	Lot size of the first trade.	▲ Higher risk
N	Max Trades (Open Layer)	Maximum number of layers the EA is allowed to open.	▲ Higher risk
S1	Step 1	Gap between the early layers.	▼ Opens less often
S2	Step 2	Gap between the later layers.	▼ Opens less often
T1	Take Profit	How far price must move before trades close in profit.	Bigger target, longer wait
E1	Lot Multiplier	How much lot size increases for each new layer.	▲ Higher risk
R1	Equity Limit	Emergency limit that protects your account equity. 1.0 = 100%, 0.2 = 20%.	▲ Less protection
P1	Slippage	Maximum accepted price difference when an order is executed.	—
P2	Lot Digits	Lot rounding to match your broker's lot rules.	—
H1	Max Trade Open Hours	Optional time limit for how long trades may stay open.	—
M1 / M2	Buy / Sell Magic Number	IDs for the EA's buy and sell orders. Change only if another EA runs on the same account.	—
F1	Use Pause Window	Turn a daily pause period on or off.	—
T2-T5	Pause Time	Pause start and end (hour and minute), Malaysia time if configured.	—
F2	Show Chart Info	Show or hide EA information on the chart.	—
F3	Use Daily Profit Target	Turn the daily profit target on or off.	—
DT1	Daily Profit Target USD	Fixed daily target in account currency (not a percentage). It does not increase automatically from the previous day.	—

Risk Controls

How to read R1 and the settings that affect risk the most.

Licence Key

Enter the licence key you received after registering. The EA will not run without a valid key.

R1 · Equity Limit values

Value	Meaning
1.0	100% equity limit. Very high — use carefully.
0.5	50% equity limit. Can trigger around half account equity loss, depending on broker conditions.
0.2	20% equity limit. More conservative.
0.1	10% equity limit. Lower exposure, but may close trades earlier.

Type it as a decimal

Enter 0.2 for 20% — not 20.

Biggest risk drivers

- **V1 Starting Lot** and **E1 Lot Multiplier** — the higher they are, the faster lot size grows.
- **N Max Trades** — more layers means more exposure when price moves against you.
- **R1 Equity Limit** — a lower value gives your account more protection.

Important

- Change one setting at a time, and test new settings on a demo account before going live.
- Make sure your capital is enough for the settings you choose. Small capital with aggressive settings can fail quickly.
- Settings can behave differently between brokers, spreads and account sizes.
- This guide is an operating reference, not a profit guarantee. Trading involves risk.