MESCO
A TRUST SINCE 1968

Navigation Menu

Admin panel guide · MESCO Trust

QA audit item 9 · September 2026

Where the navigation is managed

The header and footer navigation are maintained under **Menus**. The screen has two levels. The first lists every menu, such as Primary Menu and Footer Menu, together with how many items each one holds. Opening a menu takes you to its structure, where items are added and arranged.

Adding an item

1. Open **Menus** and click the menu you want to change.
2. Press **Add Menu**, the dashed button near the bottom of the list.
3. An item called *New item* is added. Click the small arrow on its left to expand it.
4. Fill in the fields listed below.
5. Press **Save menu**.

Field	What to enter
Navigation Label	The text visitors will see, for example *About Us*.
Type	`Page`, `Custom Link` or `Modal`. See the notes below.
Page	Shown when the type is `Page`. Pick the page from the list and the address fills in by itself.
URL	Shown when the type is `Custom Link`. Type the full web address.
PDF Link / Document	Shown when the type is `Modal`. Pick a PDF from the media library; it opens in a popup rather than leaving the page.
Target	Whether the link opens in the same tab or a new one.

Changing the order

- Drag an item up or down to move it.
- Dragging an item below another one turns it into a sub-item, so it shows as a dropdown when the menu is opened.
- The right arrow moves an item into the dropdown to its left. The left arrow brings it back out.
- Press **Save menu** once the order is right. Until you do, the new order is not applied.

Removing an item

Expand the item, press the bin icon, then press **Save menu**. To remove several at once, tick the boxes on the left and choose **Remove selected**.

Working with whole menus

Back on the first screen a menu can be copied, which is the quickest way to build a similar set of links, or deleted completely.

A few things to keep in mind

- Publishing a page does not put it in the navigation. That has to be done here.
- Use the type `Page` for anything on this website. The link then keeps working even if the page address is changed later.
- Use `Custom Link` only for outside addresses such as WhatsApp or another domain.
- If an item has been added but is not showing, the usual reason is that **Save menu** was not pressed.
- The header and the footer are separate menus, so an item added to one does not appear in the other.