



EXTENSION FOR MAGENTO 2

USER GUIDE



INTENDED AUDIENCE

The content of this document is designed to facilitate the users - managers, supervisors, and others of **Product Export List** Extension for Magento 2. A step by step instruction has been added to this document to help users to install the extension on Magento 2.

This extension will only work on Magento 2. As a safe practice always backup your files and database before installing any extension on Magento. If you are looking for someone to install the extension, we can do it for you as well. Just go to the following link and let support know the order id to expedite the installation process.

Once you have installed please see the User Guide to help you understand how to use the extension to its full capacity. If you still have questions, feel free to contact us on our website.



TABLE OF CONTENTS

Intended Audience	2
TABLE OF CONTENTS	3
USER GUIDE	
How To Configure The Extension	4
How To Enable/Disable Products To Include/Exclude From The Export List	
DISCLAIMER	



USER GUIDE

After installation of the extension, make sure the setup is upgraded and static-contents are deployed. Login to the admin panel and flush your Magento cache storage.


How To Configure The Extension

At the back end, go to STORES > Configurations. Here you can find the following settings:

GENERAL SETTINGS

- Export Only Enable Product: Select 'Yes' or 'No' to export only the enable products
- Export Only In Stock Product: Select 'Yes' or 'No' to export only the in-stock products
- Select the Visibility Criteria: Select the product visibility that you allow to see the user
- Select the Product Type: Select the product type that you allow to see the user
- Select the Customer Group: Select the customer group that you allow to see the user








PDF SETTINGS

- Enable/Disable the PDF Exporter: Option to enable/disable the PDF exporter
- Show Products For PDF: Enter a value to limit the number of products that you
 want to allow to see the user Or If you don't want to limit the number of products,
 then leave the field empty or enter zero (Note: If more attributes are selected, less
 number of products will be displayed)
- Product Attribute Setting: Add multiple products attributes with attribute heading, sorting order, column width and character per column limit of attributes (Note: Add maximum overall 555px column width for PDF)
- Text As a PDF Header: Add custom text to PDF header. Enter maximum of 300 characters
- Font Size For PDF Header: Enter the font size for PDF header text
- Font Size For PDF Heading: Enter the font size for PDF product heading text
- Font Size For PDF Text: Enter the font size for PDF text
- PDF Font Style: Option to select the font style of the text in PDF
- Show Header on All PDF Pages: Select 'Yes' or 'No' to Show/Hide the header on all the PDF pages
- Show Page Number: Select 'Yes' or 'No' to Show/Hide the page numbers
- Image As a Header For PDF Page: Upload an image to use as PDF header (Note: Allowed file types: ICO, PNG, GIF, JPEG, APNG, SVG. All browsers do not support these formats)
- Logo For Frontend PDF in Text Form: Write the custom text in place of the logo. If
 you select both image and text options for the frontend logo, then only the image is
 displayed on the frontend as a logo.









CSV SETTINGS

- Enable/Disable the CSV Exporter: Option to enable/disable the CSV exporter
- Logo For Frontend CSV in Text Form: Write the custom text in place of the logo




How To Enable/Disable Products To Include/Exclude From The Export List

At the back end, go to CATALOG > Products. Here you will find a grid of your store products. Now click on the Edit button to continue.




Now scroll down the page and Enable/Disable the product export option as per your requirements.





Note

- If there is no "Enable/Disable the product export" on the product edit page. Please add the attribute from the default settings.
- STORES -> Attributes -> Products -> Add new and fill the following fields and save it.





Advanced Attribute P	roperties
Attribute Code	enable_productslist This is used internally. Make sure you don't use spaces or more than 60 symbols.
Scope	Store View Declare attribute value saving scope.
Default Value	No 🔻
Unique Value	No Value Not shared with other products.
Input Validation for Store Owner	None
Add to Column Options	No Select "Yes" to add this attribute to the list of column options in the product grid.
Use in Filter Options	No Select "Yes" to add this attribute to the list of filter options in the product grid.

- Now open the Product Page by CATALOG -> Product -> Edit any Product.
- On the edit page, click "Add attribute".
- Select "enable_productslist" from the grid.
- Now click "Add Selected".
- Now you'll see the "Attribute" tab with a required field.





DISCLAIMER

It is highly recommended to back up your server files and database before installing this module.

No responsibility will be taken for any adverse effects occurring during installation.

It is recommended you install on a test server initially to carry out your own testing.