D

Dumbhanengue ERP

Troubleshooting

A practical guide to solving the most common day-to-day app problems. To learn how to use the system, see the User Guide.

Version 1.1.0+2 · August 12, 2026

Dumbhanengue ERP

Table of contents

How to use this guide 3

1. Sign-in and account problems 3

"I can't sign in" 3

"My account was deactivated" 3

"I typed the wrong e-mail when registering" 3

2. Product photo problems 3

"The product photo doesn't show in the list" 3

"Nothing happens when I take/pick a photo" 3

"Product added! (photo not uploaded...)" appears 4

3. Sales problems 4

"The sale won't confirm / 'Could not register the sale'" 4

"I sold by mistake / the customer didn't take it" 4

"Stock wasn't deducted / deducted too much" 4

"The label scale can't find the product" 4

4. Product and stock problems 4

"The product doesn't show in the list / checkout" 4

"Stock is negative or wrong" 5

"The expiry alert doesn't appear" 5

5. Money and finances problems 5

"The cash balance doesn't match" 5

"The cash closing shows surplus/shortage" 5

"I can't close the cash / register a purchase" 5

"The pending item doesn't enter the cash when received" 5

6. Connection and sync problems 5

"Data looks old / doesn't update" 5

"Can I use the app without internet?" 6

"The app keeps 'loading' forever" 6

7. App problems (freeze, white screen, slow) 6

"The app freezes or closes by itself" 6

"White screen / won't open" 6

"The app suddenly changed language / currency" 6

8. Common error messages 6

9. When to contact support 7

How to use this guide

1. Find your symptom below (sign-in, sales, stock, photos...).
2. Follow the steps in order — always start with the simplest.
3. If the problem persists, check Common error messages and, finally, When to contact support.

> Golden rule: before anything else, check that your phone has internet and that the app is up to date (app store). Many "errors" are just a missing connection or an old version.

---

1. Sign-in and account problems

"I can't sign in"

1. Double-check your e-mail (no spaces, correct) and password.
2. Tap "Forgot password?" if you don't remember — the link arrives by e-mail (also check spam/junk).
3. If you're a new user: the account must be approved (up to 24h). Pending approval = can't sign in.
4. Close the app completely and reopen it (sessions sometimes get stuck).

"My account was deactivated"

- The owner can deactivate employees — if that's your case, access is blocked immediately.
- Talk to the store owner to be reactivated.

"I typed the wrong e-mail when registering"

- There's no way to change the registration e-mail from the app: contact support with the correct e-mail and business name.

---

2. Product photo problems

"The product photo doesn't show in the list"

1. The product may have been saved without a photo (the upload failed — e.g., no internet). Open the product → Edit product → tap the photo area → add it again.
2. Make sure the photo was actually selected (the preview shows before saving).

"Nothing happens when I take/pick a photo"

1. The phone asks for camera/storage permission — accept it. If you declined earlier: Phone settings → Apps → Dumbhanengue → Permissions and enable Camera/Files.
2. Close and reopen the app and try again.

"Product added! (photo not uploaded...)" appears

- The product was saved — only the photo didn't upload (no internet or temporary error).
- You can add the photo later, through product edit.
- If it always happens, even with internet, contact support (it may be a server configuration).

---

3. Sales problems

"The sale won't confirm / 'Could not register the sale'"

1. Check your internet.
2. Make sure you filled in all fields (product, quantity, payment method).
3. Make sure the quantity isn't zero and the total matches the items.
4. If the sale is for a deactivated product, reactivate it (Products → Edit → Active product).

"I sold by mistake / the customer didn't take it"

- Open the sale → Cancel sale (owner/manager only). Stock returns and the cash is reversed.
- Employees don't see the Cancel button — it's a managerial operation; ask the owner/manager.

"Stock wasn't deducted / deducted too much"

1. Check the sale details to confirm the items are correct.
2. Cancelled sales return stock — if you cancelled, the stock comes back.
3. Check for purchases (increase stock) or manual adjustments in product edit.
4. If there's still a discrepancy, use the stock adjustment in product edit (owner/manager) to fix it.

"The label scale can't find the product"

- Check the barcode (PLU) registered on the product (up to 5 digits, format 20PPPPPWWWWW).
- Make sure the product is active and in the correct active store.

---

4. Product and stock problems

"The product doesn't show in the list / checkout"

1. Pull down to refresh the list.
2. Make sure you're on the correct active store (Stores → Settings → Active store).

3. Check the product isn't deactivated (Products → Edit → Active product).

"Stock is negative or wrong"

- The system won't let you sell more than exists — the "insufficient stock" error is the system protecting you.
- Fix discrepancies with the manual stock adjustment (product edit, owner/manager).

"The expiry alert doesn't appear"

- The alert appears when the product has an expiry date set (registration or purchase with a lot).
- Products without an expiry date never trigger an alert.

---

5. Money and finances problems

"The cash balance doesn't match"

1. Check for pending items (receive/pay) not yet confirmed — they only count once Receive/Pay is confirmed.
2. Cancelled sales generate a reversal — the pair (sale + reversal) closes at zero.
3. Purchases and expenses leave the cash — check for a forgotten expense.
4. Check the active store — each store has separate cash.

"The cash closing shows surplus/shortage"

- The expected in the drawer only considers physical cash (card, M-Pesa, E-Mola, transfer don't count).
- Surplus: there may be extra cash (e.g., a customer paid more, or an under-registered payment).
- Shortage: check whether a cash payment wasn't registered or money was taken from the drawer.
- Typed it wrong? You can redo the day's closing — it updates without duplicating.

"I can't close the cash / register a purchase"

- These are managerial operations (owner/manager). Employees don't have the button — ask the owner/manager.

"The pending item doesn't enter the cash when received"

- When you confirm Receive/Pay, the transaction starts counting in the realized cash. If it doesn't, refresh the screen (pull down) and check the active store.

---

6. Connection and sync problems

"Data looks old / doesn't update"

1. Pull down on lists to refresh.
2. Switch tabs and come back (the app reloads when entering the screen).
3. Check your phone's internet.

"Can I use the app without internet?"

- In online mode (default), the app needs a connection to register sales, products, etc. Without internet, operations fail — try again when the connection returns.
- Sign-in also requires internet.

"The app keeps 'loading' forever"

1. Check your internet (try opening another page/app).
2. Close and reopen the app.
3. If it's the first launch after an update, wait — it may be syncing.

---

7. App problems (freeze, white screen, slow)

"The app freezes or closes by itself"

1. Close the app (swipe it out of recent apps) and reopen it.
2. Restart your phone if it persists.
3. Check your phone's storage (very full → slow app).
4. Update the app in the app store — old versions may have fixed bugs.

"White screen / won't open"

1. Close and reopen the app.
2. Check your internet (the sign-in screen needs it).
3. If it persists, uninstall and reinstall — your data stays on the server and returns when you sign in. Uninstalling doesn't delete your business data (it's in the cloud), but make sure you know your e-mail/password first.

"The app suddenly changed language / currency"

- Currency and language are set by the owner in Stores → Settings and apply to the whole business, instantly. If it changed suddenly, a setting was changed (or on another device with the same owner account) — just go back to Stores → Settings and choose again.

---

8. Common error messages

> The messages below are approximate — the exact wording may vary slightly by app version. Look for the main idea.

Message you see (e.g.)	What it means	What to do
"Could not sign in. Check your credentials."	Wrong e-mail or password	Recover the password ("Forgot password?") or check the e-mail
"Access pending approval"	Account not yet approved	Wait for approval (up to 24h) or contact support
"Could not add the product. Try again."	Error saving the product	Check internet, required fields, and try again
"Product added! (photo not uploaded...)"	Product saved, but the photo didn't upload	Add the photo later through product edit
"Insufficient stock"	Not enough stock for the quantity	Reduce the quantity, buy more, or adjust stock
"The sale total doesn't match the items"	Sum of items ≠ total	Review items and total before confirming
"Could not cancel the sale. Try again."	Error cancelling	Check internet and that the sale is still active (not cancelled)
"Only the owner or a manager can..."	Operation restricted to owner/manager	Ask the owner/manager to do it
"Could not share the receipt"	Error sharing	Check you have sharing apps (WhatsApp) installed
"Could not export the report"	Error generating the CSV/PDF	Try again; if it persists, contact support
"Session expired / sign in again"	Old session ended	Sign in again

---

9. When to contact support

Contact support when:

- The error message persists after trying the steps above.
- The error involves money (cash, closing, sales) and the difference can't be explained.
- You suspect wrong data on the server (e.g., a sale that doesn't appear on another device).
- The app shows a new error or strange behaviour after an update.

To help support, have ready:

1. The exact message on the screen (or a screenshot).
2. What you were doing when the error happened (e.g., "registering a 3-item sale").

3. Your phone/model and the app version (Phone settings → Apps → Dumbhanengue).
4. The store and the approximate time of the problem.

Based on the User Guide — to learn how to use the app, see the User Guide.