

StakeDXF

UI & Capabilities Slide Deck

On-device Civil 3D DWG ? Trimble DXF recovery
and customizable staking plot PDFs for Trimble TSC5.

TRIO Engineering · Field Controller App


Agenda

- ? What StakeDXF does
- ? Home screen & navigation
- ? Convert DWG ? DXF workflow
- ? Export Points & plot customization
- ? Staking plot PDF examples
- ? Install on Trimble TSC5
- ? Where to find help docs

What StakeDXF does

- ? Recover Civil 3D / AEC proxy linework into stakeable DXF
- ? Import Trimble point CSV / TXT (PNEZD)
- ? Build auto-scaled staking plot PDFs on the controller
- ? Optionally overlay DXF linework by layer
- ? Customize markers, labels, and point-list table
- ? Runs entirely on-device ? no cloud upload

Home screen



Two jobs from the home screen:

1. Convert DWG ? DXF
Recover Civil 3D linework for Trimble Access stakeout.
2. Export Points
Select points, customize a staking plot PDF, or export a trimmed CSV.

Everything stays on the TSC5.

Convert DWG · DXF

9:41

TSC5

· Convert DWG

Recover stakeable linework, review layers with data, export a DXF for Trimble Access.

· Choose DWG / DXF

Convert for Trimble Access

Recovered 390 entities on 12 layer(s)

Layers with data: 12 (empty layers omitted)

Converted layers (3/12)

· P-CURB · 390 entities

· P-U-STM · 649 entities

· 0 · 26804 entities

Save DXF (3 layers)

- ? Pick a Civil 3D .dwg or .dxf
- ? LibreDWG converts DWG ? DXF on device
- ? Python (ezdxf) explodes ACAD_PROXY_ENTITY graphics
- ? Keeps Trimble-stakeable types only
- ? Save DXF into Trimble Data/Projects/<job>/
- ? Map files ? selectable ? Stakeout

Export Points · start

9:41

TSC5

· Export Points

Job name

ALPINE HILLS

Import points CSV / TXT

Link DXF linework (optional)

Import a PNEZD CSV from Trimble Access to begin.

StakeDXF · TRIO Engineering

- ? Enter a job name for the sheet title
- ? Import points CSV / TXT from Trimble Access
- ? Optionally link a matching DXF for linework
- ? Then customize markers, labels, and layers

Export Points · customize & create

9:41

TSC5

· Export Points

Job name

ALPINE HILLS

Import points CSV / TXT

Link DXF linework (optional)

Plot options

Point marker

Large X

Point label

Number + elevation

· Include point list table

· Draw linked DXF linework

Linework layers (3/3)

· CL

· CURB

· STRUCTURE

4 of 4 points selected

· 700 125 HUB

· 701 125 PK

· 702 125 PK

Create staking plot PDF

Export selected points CSV

- ? Point marker: triangle, X, cross, circle, dot?
- ? Point label: number / desc / elev combinations
- ? Point list table: off by default (more plot space)
- ? DXF layers: check only what you want drawn
- ? Select which points appear on the sheet
- ? Create staking plot PDF or export CSV

StakeDXF · TRIO Engineering

7 / 14

Plot customization options

Markers

- ? Filled triangle · Triangle outline
- ? Cross (+) · X · Large X
- ? Circle · Dot · Large dot


Labels

- ? Point number
- ? Number + description
- ? Number + elevation
- ? Number + description + elevation
- ? No labels


Layout & linework

- ? Include point list table ? optional (off by default for staking)
- ? Link DXF ? draw LINE / LWPOLYLINE / ARC / CIRCLE by layer
- ? Engineering scale auto-picked so content fits the ANSI B sheet


Staking plot examples




Field staking · large X + elev



Control-note style + table




Circles + curb layer




Cross (+) number only


Staking plot examples




Overview · dots, no labels



Dense set · number only



Grade check · elev labels



Full sheet + linework

Install on Trimble TSC5

- ? Copy dist/StakeDXF-tsc5.apk onto the TSC5 (USB or Files)
- ? Open the APK ? allow Install from this source if prompted
- ? Open StakeDXF from the app drawer
- ? If Install is blocked, ask IT to allow unknown sources / MDM exception
- ? APK is Android-only ? will not install on iPhone

Field workflow (end-to-end)

- ? Office: save Civil 3D DWG with proxy graphics preserved
- ? TSC5: Convert DWG ? DXF ? Save into Trimble job folder
- ? Trimble Access: Map files ? selectable ? stake linework
- ? Export points CSV from Access for the shots you need
- ? StakeDXF Export Points ? customize ? Create staking plot PDF
- ? Keep the PDF open while staking for a scaled field sheet

Docs & help

- ? [dist/INSTALL_TSC5.md](#) ? quick install card
- ? [dist/StakeDXF_User_Guide.pdf](#) ? full install / usage / help
- ? [docs/USER_GUIDE.md](#) ? same guide in Markdown
- ? [dist/plot_examples/](#) ? sample staking plot PDFs
- ? [PR #6](#) ? source, APK, and release notes

Ready for the field.

StakeDXF on Trimble TSC5

Recover linework. Plot points. Stake with confidence.