

Linux UFW essentials



CHECKING UFW STATUS

```
# Check UFW status
$ ufw status
```

```
# Detailed status with rules
$ ufw status verbose
```



ENABLING/DISABLING UFW

```
# Enable the firewall
$ ufw enable
```

```
# Disable the firewall
$ ufw disable
```



ALLOWING TRAFFIC

```
# Allow traffic on a specific port (e.g., 22 for SSH)
$ ufw allow <port>
```

```
# Allow traffic for a specific service (e.g., 'http', 'https')
$ ufw allow <service>
```

```
# Allow traffic from a specific IP address
$ ufw allow from <IP>
```



DENYING TRAFFIC

```
# Deny traffic on a specific port
$ ufw deny <port>
```

```
# Deny traffic from a specific IP address
$ ufw deny from <IP>
```

```
# Deny traffic for a specific service
$ ufw deny <service>
```



ALLOWING/DENYING TRAFFIC WITH CONDITIONS

```
# Allow traffic with specific protocol, IPs, and port
$ ufw allow proto <protocol> from <IP> to <IP> port <port>
```

```
# Deny traffic with specific protocol, IPs, and port
$ ufw deny proto <protocol> from <IP> to <IP> port <port>
```



DELETING RULES

```
# Delete allow rule for a port
$ ufw delete allow <port>
```

```
# Delete deny rule for a port
$ ufw delete deny <port>
```

```
# Delete allow rule for an IP
$ ufw delete allow from <IP>
```

```
# Delete deny rule for an IP
$ ufw delete deny from <IP>
```

```
# Delete allow rule with specific protocol, IP, and port)
$ ufw delete allow proto <protocol> from <IP> to any port <port>
```



UFW PROFILES AND APPLICATIONS

```
# List available application profiles
$ ufw app list
```

```
# Get detailed information about an application profile
$ ufw app info <application>
```

```
# Update application profile rules
$ ufw app update <application>
```



RESETTING UFW

```
# Reset UFW to default settings (disables UFW and removes all rules)
$ ufw reset
```



LOGGING AND MONITORING

```
# Enable UFW logging
$ ufw logging on
```

```
# Disable UFW logging
$ ufw logging off
```

```
# Set logging level (e.g., 'low', 'medium', 'high', 'full')
$ ufw logging <level>
```



RATE LIMITING CONNECTIONS

```
# Limit connections to a specific port (e.g., 22 for SSH)
$ ufw limit <port>
```

```
# Limit connections from a specific IP address
$ ufw limit from <IP>
```

```
# Limit connections with specific protocol and port
$ ufw limit proto <protocol> to any port <port>
```