

/alog

Activity log: /alog help|on|off|config|list|status|delete --yes|export --yes

Overview

/alog controls the activity log, which records each agent run as a JSONL activity file. Use it to enable or disable recording, inspect past runs, and – with the mandatory --yes guard – delete or export a specific run.

Syntax

```
/alog          Print the help table (same as /alog help)
/alog on       Enable activity logging
/alog off      Disable activity logging
/alog config   Show the activity-log configuration
/alog list     List recorded runs
/alog status   Show the activity-log runtime status
/alog delete <run-id> --yes Delete one run (guard required)
/alog export <run-id> --yes Export one run to a JSONL file (guard required)
/alog help     Print the help table
```

Options / Subcommands

Form	Description
on	Enable activity logging via <code>persist_activity_log</code> .
off	Disable activity logging.
config	Show the current activity-log configuration.
list	List recorded runs.
status	Show the activity-log runtime status.
delete <run-id> --yes	Delete the run. --yes is mandatory: run-id and the guard are validated (FR-011/012/013/014/015) and the deletion runs on a blocking thread via <code>expire_run</code> . Confirmation reports the number of removed events.
export <run-id> --yes	Export the run to <code>log/exports/export-<run-id>.jsonl</code> (FR-018/019/020/021/022/023). --yes is mandatory here too.
help	Print the help table, including the current ON/OFF state.

--help and -h are accepted as aliases of help. Unknown subcommands print the usage text.

Examples

```
/alog on
```

Starts recording run activity.

```
/alog list
```

Lists the recorded runs so a run-id can be copied for delete/export.

```
/alog status
```

Shows the runtime status of activity logging.

```
/alog delete 9c3f1b2a --yes
```

Deletes run 9c3f1b2a after the --yes guard, confirming the number of events removed.

```
/alog export 9c3f1b2a --yes
```

Writes log/exports/export-9c3f1b2a.jsonl containing that run's events.

```
/alog help
```

Prints the help table including the current ON/OFF state.

Output

on/off confirm the state change (persist failures surface as warnings). config, list, and status print their respective views. delete prints a confirmation with the event count; without --yes the command is refused. export prints the written path log/exports/export-<run-id>.jsonl; without --yes it is refused. help prints the table with the live ON/OFF state.

Related

- /log clear research clears logs/research/, a sibling log root.
- /editlog – the separate edit-operation log.
- log/exports/ – destination for /alog export.