/triggers

Manage trigger rules: /triggers [list|enable|disable|remove|status|help]

Overview

`/triggers` manages trigger rules: conditions that fire an action automatically (for example, running a command when a file appears). Rules are not created by this command – they are created by natural language elsewhere (e.g. "when $HOME/build.done exists, run cargo test") – so `/triggers` lists, toggles, removes, and reports metrics for the existing rule set.

Syntax

```
/triggers                List trigger rules (same as /triggers list)
/triggers list           List trigger rules
/triggers enable <rule_id>    Enable a rule
/triggers disable <rule_id>   Disable a rule
/triggers remove <rule_id>    Remove a rule
/triggers status         Show runtime metrics
/triggers help           Print the usage table
```

Options / Subcommands

Form	Description
`list` (or bare)	Print a table of rules: ID (8-character prefix), condition, action, mode (`once` or `repeat`), and status (`active`, `disabled`, or `fired`). With no rules defined, prints the empty-state message explaining that rules are created by natural language.
`enable <rule_id>`	Enable the rule with the given ID prefix.
`disable <rule_id>`	Disable the rule so it no longer fires.
`remove <rule_id>`	Delete the rule.
`status`	Print runtime metrics: total/active/disabled/fired counts, dedup cache entries, cycle trackers, dedup window seconds, and max cycles.
`help`	Print the usage table.

Unknown subcommands print a warning.

Examples

`/triggers list`

Shows the rule table (ID, condition, action, mode, status) or the empty-state explainer if none exist yet.

`/triggers enable 3f9a2c`

Re-enables the rule whose ID prefix is `3f9a2c`.

`/triggers disable 3f9a2c`

Stops the rule from firing without deleting it.

`/triggers remove 3f9a2c`

Deletes the rule.

`/triggers status`

Prints the metrics table: total, active, disabled, fired, dedup cache entries, cycle trackers, dedup window secs, max cycles.

`/triggers help`

Prints the usage table.

Output

`list` prints the fixed-width rule table, or the empty-state note that rules are created by natural language. `enable`/`disable`/`remove` confirm the change for the given ID prefix. `status` prints the runtime metrics table. `help` prints the usage table; unknown subcommands print a warning line.

Related

- Natural-language rule creation (rules are made by asking the agent, not by a slash-command form).
- `/status` – unrelated; shows status-message history.