

Tools Required


SDKPerf Tool

Overview

In this course, you will be using SDKPerf to do some messaging on your PubSub+ Event Broker. SDKPerf is a tool for validating performance, checking configuration, and exploring features associated with your Solace PubSub+ event broker.

Architecture

The SDKPerf tools all share a common architecture across all the supported APIs and platforms. The following figure shows this architecture at a high level. Because SDKPerf is a tool for testing messaging, internally it is modeled as a common core and a bunch of messaging client's implementations. The SDKPerf core platform exposes a client interface which it uses to generically interact with clients across any API. This allows for the SDKPerf tool to work in the same manner across all APIs and protocols it supports. This is depicted in the architecture figure where you can see that for each API or protocol there is a corresponding SDKPerf client implementation that makes use of the API protocol and implements SDKPerf's client interface. This allows the SDKPerf platform to code to focus on the performance and functional testing required in a client-agnostic way.



Application Flow

As a command line application SDKPerf will follow a specific application flow for a given invocation. On each invocation of SDKPerf it will do the following:

- Connect clients
- Add any required subscriptions and/or bind to endpoints
- Start publishing
- Wait until publishing is done
- Remove any subscriptions that were added
- Disconnect clients
- Cleanup and report stats

Step 1: Get SDKPerf Tool

Here is a link to download: <https://solace.com/downloads/>, Here are the <https://docs.solace.com/SDKPerf/Command-Line-Options.htm>





Figure 1: Download the Java one for this course

Step 2: Extract the SDKPerf zip file downloaded

Extract the zip folder you have downloaded in the earlier step with the tool of your choice.

Step 3: Run tool on command line

Here are some commands to test your application. If a command has '-stl', it means SDKPerf is starting a subscribing client and if it has '-ptl' it means SDKPerf is starting a publishing client. Make sure to run both subscribing and publishing client on separate terminal shells (2nd and 3rd command)



```
$ ./sdkperf_java.sh -h

$ ./sdkperf_java.sh -cip={{BrokerIpAddress}} -cu=default@test_vpn -cp=password -stl="news/sports/>" -md -q

$ ./sdkperf_java.sh -cip={{BrokerIpAddress}} -cu=default@test_vpn -cp=password -ptl="news/sports/football" -mn=10
```