

G.E.T.S.

CTCL ADMIN User Manual

Version 2.0.0

GreekSoft Technologies Pvt. Ltd.
507, 5th Floor, Western Edge - 1,
Western Express Highway,
Borivali (East)
Mumbai - 400 066.

Proprietary Notice

This document contains confidential information of GreekSoft Technologies Pvt. Ltd., which is provided for the sole purpose of permitting the recipient to application help document submitted herewith. In consideration of receipt of this document, the recipient agrees to maintain such information in confidence and to not reproduce or otherwise disclose this information to any person outside the group directly responsible for evaluation of its contents, except that there is no obligation to maintain the confidentiality of any information which was known to the recipient prior to receipt of such information from GreekSoft Technologies Pvt. Ltd., or becomes publicly known through no fault of recipient, or is received without obligation of confidentiality from a third party owing no obligation of confidentiality to GreekSoft Technologies Pvt. Ltd.


INDEX

- I. User*
- II. Surveillance*
- III. Trade and Position Monitoring*
- IV. Arbitrage Surveillance*
- V. Banned Scrip Setting*
- VI. Tools*
- VII. Product*


I. User:

Connection Information:

Administrator can watch connected user through User – Connection information.




Administrator can disconnect the user. After disconnection the user, the message display on the client side 'Admin has Disconnected the Service'



User List:

All user list display with,


Group ID, User Id, User Name, Category, Status, Broker Name, Branch name, pin code, Trading allowed(Market seg), NSEEqBranchId, NSEEqTwsId, NSEFoBranchId, NSEFoTwsId, NSECurBranchId, NSECurTwsId, BSEEqBranchId, BSEEqTwsId, MCXSXBranchId, MCXSXTwsId, MCXBranchId, MCXTwsId, USETwsId, NCDEXBranchId, NCDEXTwsId, Address, Telephone, Fax, Mobile, E-Mail, PAN No, Mapped Admin, User Creation Date, Active or deactivate date.



Group	User Id	User Name	Category	Status	Broker Name	Branch Name	Pin Co	Trading Allowed	NSEEqBranch	NSEEqTws	NSEFoBranch	NSEFoTws	NSECurBranch	NSECurTws
HO	NIRAV	nirav	Dealer	Active		kandivali	30101	NSE EQ,NSE FO,	999	6	999	6		
HO	TEST1	TEST1	Dealer	Active		MUMBAI	30101	NSE EQ,NSE FO,	542	52	632	789		
HO	KIRAN	Kiran Dhavka	Dealer	Active		Kandivali	30101	NSE EQ,NSE FO,	12	11	12	11		
HO	TEST4	hitesh	Dealer	Active		kandivali	30067	NSE EQ,NSE FO,	9	1	9	1		
HO	SANJAY	SANJAY KOLI	Dealer	Active		kandivali	30101	NSE EQ,NSE FO,	6	2	7	2		
HO	GANESH	GANESH	Dealer	Active		KANDIVALI	30101	NSE EQ,NSE FO,	4	9	5	9		
HO	ANIL1	anil	Dealer	Active		ase	30101	NSE EQ,NSE FO,	2	41	2	42		
HO	IMRAN	imran	Dealer	Active		borivali	30067	NSE EQ,NSE FO,	2	5	6	4		

User Management:

User / Client Management module is for adding / modifying / deleting of users / clients in the CTCL server. The dialog can be accessed from User menu -> User Management.



User Management

Details

Group Id *: HO User Status *: Normal User Address

Category *: Dealer User/Client Id *: PRAKASH

Client Name *: prakash City:

Password *: Pin Code *: 400101 Tele: 12345456

Branch Name *: pra Participant ID: Fax: 123456

PAN No.:

Mapped to*: Group Admin Activation / Deactivation *: Active Date: 01/15/11 Mobile: 0

E-Mail Id:

IP Address *: 192 . 168 . 206 . 28

Markets Allowed TWS BranchId *

Markets Allowed	TWS	Branch Id	Member ID	User ID
☒ NSE EQ	117	001	13598	39548
☒ NSE FO	117	001	13598	30234
☒ BSE EQ	118	001	9051	201
☐ MCX FO				
☒ Automated				
☐ ATS				
☐ NCDEX FO				

Search Add New Modify Delete Upload File Upload Retailers Cancel

G.E.T.S. User Management <No Scrip>

Group Id: HO

User Status: Normal User / Admin

Category: Dealer / Retail / Group Admin / Mini Admin

Dealer – CTCL login ID for trading

Retail – Client Account ID

Group Admin – CTCL login ID for monitoring

Mini Admin – Mapped CTCL login ID for monitoring (Positions and trades)

User / Client ID: Mention the User / Client ID (Minimum 3 characters)

Client Name: Name of the User / Client Account

Password: (Default password is the user name itself)

Broker ID: Trading Member ID

Branch Name: Branch Name

Pin Code: Pin Code as per the ENIT terminal information (Only for Dealer / Group Admin Category)

PAN No.: For Retail category

Participant ID: For Institutional Client Accounts (Only for Retail Category)

Active / Suspended: To update the status of the ID; select active

Mapped To: USER mapped to Admin or Mini admin for Monitoring.

IP Address: To login particular ID from particular IP (Flag have to mention in the Manager trading style – ‘USE_IPADDRESS_1’)

Activation/ Deactivation: To active or suspend ID.

Updating CTCL terminal details:

Markets Allowed: Tick the market segment allowed for the user (Only for Dealer / Group Admin Category)

NSE EQ / NSE FO / BSE EQ / MCX FO / NCDEX FO / NSE CD / MCX-SX /
USE / Manual Not Allowed.

Automated – Tick if automated trading needs to be enabled

Manual Not Allowed – Tick if manual trading not allow needs to be enabled

TWS ID: TWS ID of market segment

Branch ID: Branch ID of market segment


Member ID: Trading Member ID of respective market segment

User ID: CTCL ID of respective market segment that is configured on Manager

City, Address, Telephone, Fax, Mobile, E-Mail ID

Unlock GETS Client / Reset Password:

On entering 3 times wrong password, GETS client will be locked. In this case, client needs to be unlocked from ADMIN terminal from User -> Set Client Password dialog. To unlock, admin needs to enter the respective User ID and modify. To reset password, admin has to select the user id, enter the new password and modify.




The dialog box titled "Set Client Password" contains the following fields and controls:

- User ID :** A dropdown menu with "TEST1" selected.
- Unlock Client :** A radio button.
- Set New Password :** A radio button, which is currently selected.
- Password :** A text input field.
- Confirm Password :** A text input field.
- Modify :** A button.
- Cancel :** A button.

Dealer Client Mapper

Admin can map the clients to dealers from this dialog.




The dialog box titled "Dealer InvestorClient Mapper" contains the following fields and controls:

- Group ID :** A dropdown menu with "HO" selected.
- Dealer ID :** A dropdown menu with "TEST1" selected.
- Save :** A button.
- Cancel :** A button.
- Available Investors :** A table with columns "Investor I" and "Investor Client Nan".
- Added Investors :** A table with columns "Investor I" and "Investor Client Nan".
- Add > :** A button.
- < Remove :** A button.
- Add All >> :** A button.
- << Remove All :** A button.

At the bottom of the dialog, there is a status bar showing "G.E.T.S Dealer Investor Client Mapper" and "Dealer: TEST1".

Arbitrage Mapper


Admin map arbitrage product with respective exchange.



II. Surveillance:

Surveillance Limitations

Admin can set the surveillance limits at User / Client level from Surveillance -> Surveillance Limits dialog. He can set below limits.



Single Order Qty – Maximum Single Quantity
 Single Order Value – Maximum Single Value (in Lacs)
 Buy Qty – Maximum Overall Buy Quantity
 Buy Value - Maximum Overall Buy Value (in Lacs)
 Sell Qty - Maximum Overall Sell Quantity
 Sell Value - Maximum Overall Sell Value (in Lacs)
 Net Qty - Maximum Overall Net Quantity
 Net Value - Maximum Overall Net Value (in Lacs)
 MtoM Limit – Maximum Mark to Market Limit
 Price % Change – Maximum LTP Percentage Change Check While Order Submission (loss side)
 Eq Buy Value: Maximum Equity Buy Value (in Lacs)
 Eq Sell Value: Maximum Equity Sell Value (in Lacs)
 Eq Net Value: Maximum Equity Net Value (in Lacs)

For Admin, additional two surveillance mention, which use for all the clients.

1) Market Order Limit :
(Market Order Limit will be generate for loss side)

From more protection algo market order won't generate on (0.00) price it will generate on LTP %.

Ex. LTP is 5000 then order will generate for BUY ($5000 + 3\% = 5150$)

LTP is 5000 then order will generate for SELL ($5000 - 3\% = 4850$)

2) Price Protection :

This surveillance is restrict wrong trade in volatile market at minimum time.

Time = Time interval in second for LTP

STOCK = Equity / Stock (Future stock) / Commodity %

INDEX = Index symbol (Nifty,Banknifty) %

OPTION = Option symbol. %

Example :

If the LTP for INDEX (10% surveillance for Index)

9:15:00 Nifty 4800 and Interval time is 120 seconds, price range will be (4320 to 5280 for Next 120 seconds). Algo order gets stopped if LTP get change below or above the range.

After 120 Seconds new LTP will get consider till next Interval.

9.17.00 New LTP price range get consider till Next Interval.

Same Surveillance checks for EQ/STK/COM & OPTION which % mention in the Price Protection.

III. Trade and Position Monitoring

Admin can monitor the online intraday position taken by the users / clients. All the trades that happen at the GETS client level will also get updated at the ADMIN level.

Admin can also apply filters and monitor the positions at market segment / symbol / user / client level. Admin can also view the live MToM across users / clients or at particular user / client.

Admin is not allowed to place any orders from his terminal. But he can cancel the pending orders of other users from pending order book.

IV. Arbitrage Surveillance

Arbitrage Surveillance is for setting the limits for automated arbitrage modules.

Admin has to set the arbitrage surveillance for the users on daily basis. If the settings are not done then rule addition in automated arbitrage modules is not allowed at client end saying “*There is no arbitrage surveillance for the user <USERID>*”.

Admin can set the arbitrage setting for selected user / all users. If he wants to set for all users, he needs to tick the check box aside All Users label.

Admin can set the arbitrage setting for selected arbitrage type / all types. If he wants to set for all types, he needs to tick the check box aside All Types label. *At present this applies for Cash to Future quote and Future to Future quote models only.*

Max Number of Rules (Maximum no. of arbitrage rules per arbitrage type) - *40 rules max*

Max Number of Order Lots per rule - *100 lots max*

Max Number of Total Lots per rule (Overall limit) – *999 lots max*

Max Threshold Qty Allowed in % (Max Th Qty available in depth) – *999 max*


Market Protection Limit in (%) – *10/%* (maximum 10% loss side rules will be add)

Order Opportunity in (%) – *20* (order won't be generate below or upper, at difference of the rule with calculation of LTP)

If the admin wishes to modify, he can select the respective arbitrage setting from grid, update the data and modify the settings. Any particular setting can also be deleted, upon which the respective user cannot able to add any new rule in the arbitrage type.

Upon execution of trades, the total quantity will get reduced by the traded quantity.

Admin can click on the Setting button and save the selected values as default values.



The dialog box titled "Arbitrage Surveillance Setting" contains the following fields and controls:

- User ID : ☐ All Users /
- Arbitrage Type : ☐ All Types /
- Max Number of Rules : *
- Max Number of Order Lots per rule : *
- Max Number of Total Lots per rule : *
- Max Threshold Qty Allowed in (%) : *
- Market Protection Limit in (%) : *
- Order Opportunity in (%) : *

Below the input fields are buttons:

Chk	User ID	Arbitrage Type	Rule Limit	Order Lot	Total Lot	Threshold
☒	PRAKASH	GETS IV ORDER ENTRY	100	100	100	
☐	PRAKASH	GETS ROLL OVER	100	100	100	
☐	PRAKASH	GETS QUOTE	100	100	100	
☐	PRAKASH	GETS QUOTE	100	100	100	
☐	PRAKASH	GETS EXCEL	100	100	100	
☐	PRAKASH	GETS DYNAMIC	100	100	100	
☐	PRAKASH	GETS BSE LEI	100	100	100	
☐	PRAKASH	GETS BSE LEI	100	100	100	
☐	PRAKASH	GETS SLICE	100	100	100	
☐	PRAKASH	GETS ETF	100	100	100	
☐	PRAKASH	GETS	100	100	100	

V. Banned Scrip Setting

Admin can block trading in automated modules in particular scrip from banned scrip setting dialog. This can be accessed from Surveillance -> Banned Scrip Setting.

Admin can set the banned scrip setting for selected user / all users. If he wants to set for all users, he needs to tick the check box aside All Users label. He has to select the banned scrip, market segment (E for EQUITY, F for FUTURE and O for OPTION) and Expiry.

If the admin wishes to delete, he can select the respective setting from grid and delete the setting.

UserID	Product	Symbol	Expiry	MktType
TEST1	GETS QUOTE COC	BAJAJHIND	24SEP2009	F
TEST1	GETS QUOTE COC	BEL	-----	E
TEST2	GETS QUOTE COC	BAJAJHIND	24SEP2009	F
TEST2	GETS QUOTE COC	BEL	-----	E
TEST3	GETS QUOTE COC	BAJAJHIND	24SEP2009	F
TEST3	GETS QUOTE COC	BEL	-----	E
TEST4	GETS QUOTE COC	BAJAJHIND	24SEP2009	F
TEST4	GETS QUOTE COC	BEL	-----	E
TEST5	GETS QUOTE COC	BAJAJHIND	24SEP2009	F
TEST5	GETS QUOTE COC	BEL	-----	E
TEST8	GETS QUOTE COC	BAJAJHIND	24SEP2009	F
TEST8	GETS QUOTE COC	BEL	-----	E

VI. Tools:

Expense Setting

Admin can define the expense settings, which helps him to track the expenses on each trade received across users / at particular user. The expense calculated will be shown under expense column in net position dialog.

Various parameters those need to be filled in expense settings are explained below.

Exchange Type – Exchange Selection

Market Segment – EQUITY / FUTURE / OPTION

Expense Type – Brokerage/Service Tax/Transaction Charges/STT/Stamp Duty/SEBI Tax

Trade Type – Turnover / Square-off / Non Square-off

Expense on – Buy / Sell / Both

Charges Type – Changes on selection of Market Segment and Trade Type

Expense Rate – Input the expense rate for the selected rule

Base Rate – Base rate on which expense rate is calculated

The Expense Settings dialog box contains the following sections:

- Date:** Start Date* (9/15/2009)
- Basis:** ☒ Daily ☐ Expiry
- Types:**
 - Exchange Type*: NSE
 - Expense Type*: Brokerage Tax
 - Expense On: BOTH
 - Mkt Seg*: EQUITY
 - Trade Type*: NON SQUARE OFF
- Charges Type:** ☒ Delivery ☐ Non Delivery
- Rates:**
 - Expense Rate: 1700.00
 - Base Rate: 10000000.00
- Buttons:** Add New, Modify, Delete, Save File, Upload File, Apply
- Table:**

Start Date	Exchange	Expense Typ	Market Segm	Expense On	Expense Rat	Base Rate	Basis
15-Sep-2009	NSE	Brokerage T.	OPTION	BOTH	1700.00	10000000.00	
15-Sep-2009	NSE	Brokerage T.	FUTURE	BOTH	1500.00	10000000.00	
15-Sep-2009	NSE	Stamp Duty	EQUITY	SELL	180.00	10000000.00	
15-Sep-2009	NSE	Brokerage T.	EQUITY	BOTH	1700.00	10000000.00	
15-Sep-2009	NSE	Brokerage T.	EQUITY	BUY	2500.00	10000000.00	

Trade Log

Administrator can view previous trades from Trade Log. He can give filter to Exchange, USER and Symbol. After selection of Dates he presses Fetch data. Administrator save fetched data, it will be saved in CTCL folder – Previous Backup.

Chat

Admin can send message to selective user or all users.

VII. Product:

Arbitrage Logoff

Admin can get to know all login algorithm products with user id and Login time.
After check the box of the product admin can disconnect the arbitrage product.

-----**END OF DOCUMENT**-----