



Lab 3 Submission


Question 1



Question 2



Question 3



Challenge Question

```

Tilix: thecoon@thecoon: ~
1: thecoon@thecoon: ~
thecoon@thecoon:~$ free -h -L
SwapUse      1.3Gi  CachUse      541Mi  MemUse      1.5Gi  Mem
Free          176Mi
thecoon@thecoon:~$

2: thecoon@thecoon: ~
-h, --human
    Show all output fields automatically scaled to
    shortest three digit unit and display the units
    of print out. Following units are used.

    B = bytes
    Ki = kibibyte
    Mi = mebibyte
    Gi = gibibyte
    Ti = tebibyte
    Pi = pebibyte

    If unit is missing, and you have exbibyte of RAM
    or swap, the number is in tebibytes and columns
    might not be aligned with header.

-w, --wide
    Switch to the wide mode. The wide mode produces
    lines longer than 80 characters. In this mode
    buffers and cache are reported in two separate
    columns.

-c, --count count
    Display the result count times. Requires the -s
    option.

-l, --lohi
    Show detailed low and high memory statistics.

-L, --line
    al page free(1) line 85/158 71% (press h for help or q to quit)

```



```

Tilix: thecoon@thecoon: ~
1: thecoon@thecoon: ~
thecoon@thecoon:~$ uname -s -r -v -o
Linux 6.12.73+deb13-amd64 #1 SMP PREEMPT_DYNAMIC Debian 6.12.73
-1 (2026-02-17) GNU/Linux
thecoon@thecoon:~$

2: thecoon@thecoon: ~
-s, --kernel-name
    print the kernel name

-n, --nodename
    print the network node hostname

-r, --kernel-release
    print the kernel release

-v, --kernel-version
    print the kernel version

-m, --machine
    print the machine hardware name

-p, --processor
    print the processor type (non-portable)

-i, --hardware-platform
    print the hardware platform (non-portable)


-o, --operating-system
    print the operating system

--help display this help and exit

--version
    output version information and exit

AUTHOR
Manual page uname(1) line 17 (press h for help or q to quit)

```



```
1: thecoon@thecoon: ~  
thecoon@thecoon:~$ date --iso-8601=ns  
2026-02-23T19:45:53.020790090-05:00  
thecoon@thecoon:~$  
2: thecoon@thecoon: ~  
like --date; once for each line of DATEFILE  
-I[FMT], --iso-8601[=FMT]  
output date/time in ISO 8601 format. FMT='date'  
for date only (the default), 'hours', 'minutes',  
'seconds', or 'ns' for date and time to the in-  
dicated precision. Example:  
2006-08-14T02:34:56-06:00  
--resolution  
output the available resolution of timestamps  
Example: 0.00000001  
-R, --rfc-email  
output date and time in RFC 5322 format. Exam-  
ple: Mon, 14 Aug 2006 02:34:56 -0600  
--rfc-3339=FMT  
output date/time in RFC 3339 format.  
FMT='date', 'seconds', or 'ns' for date and time  
to the indicated precision. Example: 2006-08-14  
02:34:56-06:00  
-r, --reference=FILE  
display the last modification time of FILE  
-s, --set=STRING  
set time described by STRING  
-u, --utc, --universal  
al page date(1) line 25/242 27% (press h for help or q to quit)
```

Challenge Question Script Source code:

[lab3](#)