


Interstate '76: Keyboard and mouse

i76-everywhere control map (WASD-style). This is not the 1997 key layout; the last page compares the two.



Key colour and corner letter = group. Shift + arrow keys move the outside camera and the map. Keys with no label are not bound. F-keys and Esc are engine keys, not in input.map.

D Driving	W Weapons	T Targeting	V Views	S Systems	Mouse
Throttle / brake, analog Steer, analog Accelerate Brake Steer left Steer right Gear down Gear up Handbrake Reverse (toggle) Ignition (start engine)	Joystick 1 Y Joystick 1 X W S A D , . , Space X I	Fire selected weapon Cycle weapon Link weapons Fire hardpoint 1 Fire hardpoint 2 Fire hardpoint 3 Fire hardpoint 4 Fire hardpoint 5 Special 1 (nitrous slot) Special 2 Special 3	Enter Tab F J L 3 4 5 6 7 8 Q Y T U R K	Up Down Left Right E V B Shift + arrows PgUp PgDn End F1 F3 F2 F7 F8 F9 F10	M N H G P ' ; Esc Map Notepad Headlights Horn Poetry Player scores (multiplayer) Team scores (multiplayer) Pause menu / skip cutscene
		Target in front Next target Target nearest enemy Clear target Radar range Radar camera			Left button Middle button Right button Button 4 (back) Button 5 (forward) Wheel up Wheel down
					Fire selected weapon Look left Fire hardpoint 2 Special 1 (nitrous slot) Fire hardpoint 3 Cycle weapon Fire hardpoint 5

Status. Map: the owner's daily-driver map of 2026-10-03 plus three keys added the same day (1 and J = hardpoint 1, L = hardpoint 2); the daily driver gets them by promotion after a pad test. The dedicated arrow keys look around and W A S D drive (owner, 2026-10-03). A fresh install made by INSTALL.bat has not been started by anyone on this project (INSTALL.md, Evidence): on such an install this page is read from the files, not played. Buttons 4 and 5 need the AutoHotkey layer (i76-remap.ahk); the wheel needs i76wheel.exe, started by PLAY-i76.ps1. Status of the wheel helper: not recorded (ENHANCEMENTS.md).

LT (left trigger)
Fire hardpoint 2 *(hold)* 2

LB + Fire hardpoint 5 + Fire hardpoint 2 *(hold)*
5 2

LB (left bumper)
Target in front *(tap; hold = SHIFT)* Q

LS (left stick)
Throttle / brake, analog native: joystick1 Down/Up
Steer, analog native: joystick1 Left/Right

L3 (press left stick)
Special 1 (nitrous slot) *(hold)* 6
Reverse (toggle) *(pressed with the left stick pulled back)* X

D-pad up
Headlights H

LB + Binoculars B

D-pad down
Ignition (start engine) I

LB + Horn *(hold)* G


D-pad left
Notepad N

LB + Gear down ,

D-pad right
Map M

LB + Gear up .

Back / Select
Pause menu / skip cutscene Esc



Hold LB for the shift layer (the **LB +** lines). Small grey text is the key the AutoHotkey layer types. The left stick is the only native binding: without the layer (i76-remap.ahk, started by PLAY-i76.bat) the buttons do nothing.

Status. Pad layer: "deployed, verified on Mac/Windows" (RELEASE-PLAN section 1). The docs do not record a play test of the pad on this map. Changed 2026-10-03 and not yet played: LB + D-pad left / right (gears), B (cycle weapon), LB + RT (hardpoint 1), RB (handbrake). Connect the pad before launching. Without the AutoHotkey layer a pad has the left stick only: this map binds no pad button natively.

RT (right trigger)
Fire selected weapon *(hold)* Left mouse button
Fire hardpoint 3 *(while the right stick is held back (rear view))* 3

LB + Fire hardpoint 1 *(hold)* 1

RB (right bumper)
Handbrake *(hold)* Space

Y
Chase camera + Cockpit view *(alternates)* F3 F1

LB + Cycle camera views *(one step per press)*
F1 F2 F3 F7 F8 F9 F10

X
Next target Y

LB + Radar range R

B
Cycle weapon *(tap)* Tab

LB + Fire hardpoint 4 *(hold)* 4

A
Fire selected weapon *(tap; types a click and Enter: OK in menus, one shot in the car)*
Left mouse button Enter
Special 1 (nitrous slot) *(hold 0.4 s)* 6

LB + Fire hardpoint 3 *(hold)* 3

RS (right stick)
Look around *(held while deflected)*
Up Down Left Right

R3 (press right stick)
Look at target E
Fire hardpoint 4 *(while the right stick is held back)* 4

Start
Map M

1 L1 left paddle

Headlights H

6+ Fire selected weapon Left mouse button

D-pad up

Headlights H

6+ Gear up .

D-pad right

Map M

D-pad down

Ignition (start engine) I

6+ Gear down ,

D-pad left

Notepad N

7 SHARE (SE)

Fire hardpoint 3 3

6+ Fire hardpoint 4 4

10 L2


Horn G (hold)

6+ Radar range R

11 L3

Headlights H

6+ Radar camera K



pedals: throttle / brake · rim: steer (native, no layer needed)

Hold button 6 (the lowest face button) for the shift layer: the 6+ lines. Small grey text is the key i76-remap.ahk types; buttons with *(hold)* keep their key down while pressed, the rest tap once. Steering and pedals are native (input.map) and work without the layer.

The black badge is the PC button number (Thrustmaster manual). The picture is a schematic of the PS4-layout rim; the face-button numbers follow the order the manual lists them (△ □ ○ × = 3 to 6) and have not been press-tested by symbol: if one is off, the numbers on the boxes are what counts.

Status. Wheel: "STATUS 2026-08-01: WORKING AND PLAYED" (WHEEL-T300.md). Buttons rebalanced 2026-08-08; of the rebalanced buttons the docs record only the held horn as confirmed in the game (FIGHTERSTICK.md).

2 R1 right paddle

Fire selected weapon Enter (hold)

6+ Target in front Q

3 △ face button

Cycle weapon Tab

6+ Combat view (toggle) V

4 □ face button

Handbrake Space (hold)

6+ Reverse (toggle) X

5 ○ face button

Special 1 (nitrous slot) 6

6+ Special 2 7

6 × face button: SHIFT (hold)

SHIFT (hold)

8 OPTIONS

Target nearest enemy T

6+ Clear target U

9 R2

Horn G (hold)

6+ Look at target E

12 R3

Ignition (start engine) I

6+ Binoculars B

13 PS

Horn G (hold)

6+ Poetry P

▲ Look down Down

◀ Look left Left

cone

▶ Look right Right

▼ Look up Up

▲ Fire hardpoint 2 2

◀ Fire hardpoint 5 5

hat

▶ Fire hardpoint 3 3

▼ Fire hardpoint 4 4

▲ Reverse (toggle) X

◀ Gear down ,

stick

▶ Gear up .

▼ Handbrake Space

2 pickle

cone (POV)

convex 5-8

trim 13-16

castle 9-12

3 MODE (back)

1 trigger

4 pinky

forward = reverse · back = handbrake · left / right = gear

▲ Target in front Q

◀ Radar range R

hat

▶ Next target Y

▼ Target nearest enemy T

▲ Special 1 (nitrous slot) 6

◀ Map M

hat

▶ Notepad N

▼ Combat view (toggle) V

1 trigger

Fire selected weapon Enter

2 top red (pickle)

Fire hardpoint 2 2

3 back-side (MODE)

Special 1 (nitrous slot) 6

4 pinky red

Look at target E

All stick controls are typed by i76-ch-fighterstick.ahk. Forward = reverse only while held; back = handbrake while held; left / right = one gear per movement. Weapon link is on the keyboard (F) only. The picture is a schematic of the grip; hat and button names follow FIGHTERSTICK.md.

Status. Stick: "Confirmed in the game, 2026-08-08, control by control": trigger, the three hats, special 1, cone-hat glance, stick axes (FIGHTERSTICK.md). Pickle (2) and pinky (4) are not in that table.

i76-everywhere · controls/input.map md5 90122d370333b545d27070f3f94b1265 · generated 2026-10-04 · page 4 of 5 · regenerate: tools\controls-sheet\build.ps1

Interstate '76: Stock 1997 keys vs ours

i76-everywhere control map (WASD-style). This is not the 1997 key layout; the last page compares the two.

● = **changed** (23 of 46 rows). Every letter, number and punctuation key is ignored while Shift or Ctrl is held, in both maps.

Action	1997 keys	This project
Throttle / brake, analog	<i>not bound</i>	Joystick 1, forward / back axis ●
Steer, analog	<i>not bound</i>	Joystick 1, left / right axis ●
Accelerate	Up arrow (plain set)	W ●
Brake	Down arrow (plain set)	S ●
Steer left	Left arrow (plain set)	A ●
Steer right	Right arrow (plain set)	D ●
Gear down	, (comma)	, (comma)
Gear up	. (period)	. (period)
Handbrake	Z	Space ●
Reverse (toggle)	Tab	X ●
Ignition (start engine)	S	I ●
Fire selected weapon	Space	Enter ● Left mouse button
Cycle weapon	Enter	Tab ●
Link weapons	L	F ●
Fire hardpoint 1	1	1 ● J
Fire hardpoint 2	2	2 ● Right mouse button L
Fire hardpoint 3	3	3
Fire hardpoint 4	4	4
Fire hardpoint 5	5	5
Special 1 (nitrous slot)	6	6
Special 2	7	7
Special 3	8	8
Target in front	Q	Q

Action	1997 keys	This project
Next target	E	Y ●
Target nearest enemy	T	T
Clear target	Y	U ●
Radar range	R	R
Radar camera	W	K ●
Look up	Down arrow	Up arrow ●
Look down	Up arrow	Down arrow ●
Look left	Left arrow	Left arrow ● Middle mouse button
Look right	Right arrow	Right arrow
Look at target	Insert	E ●
Combat view (toggle)	V	V
Binoculars	B	B
Move outside camera / pan map	Up arrow Left arrow Right arrow Down arrow	Shift + Up arrow ● Shift + Down arrow Shift + Left arrow Shift + Right arrow
Zoom minus (view, map, camera)	Page Up	Page Up
Zoom plus (view, map, camera)	Page Down	Page Down
Zoom reset	End	End
Map	M	M
Notepad	N	N
Headlights	H	H
Horn	G	G
Poetry	C	P ●
Player scores (multiplayer)	' (quote)	' (quote)
Team scores (multiplayer)	; (semicolon)	; (semicolon)

Status. 1997 column: input.map of GOG's offline installer 2.1.0.17 (stock-2.1.0.17.json). Its plain arrow tokens (UpArrow ...) versus the Grey set have not been checked on a Windows keyboard by anyone on this project. To keep the 1997 keys: setup-windows.ps1 -GameDir <game folder> -Controls stock -ControlsOnly