



Outlook

FW: Execution of Field Mapping Conversions During Migration Cockpit Data Loads

From Somanchi, Brahma <brahma.somanchi@capgemini.com>

Date Wed 2026-05-27 10:36

To Battaglin, Thiago <thiago.battaglin@capgemini.com>

From: Kotha, Ramya <ramya.kotha@capgemini.com>

Sent: Tuesday, May 26, 2026 12:44 PM

To: Somanchi, Brahma <brahma.somanchi@capgemini.com>; Sharma, Praful <praful.sharma@capgemini.com>; Kanamukkala, Anusha <anusha.kanamukkala@capgemini.com>; Hernandez, Hector <hector.hernandez@capgemini.com>; Battaglin, Thiago <thiago.battaglin@capgemini.com>

Cc: Lau, Rocky <rocky.lau@capgemini.com>

Subject: Execution of Field Mapping Conversions During Migration Cockpit Data Loads

Hi team,

Below are the details regarding the conversions currently maintained in the field mappings for different migration objects.

These are common conversion rules available across migration objects; however, there may also be migration-object-specific conversions depending on the object and its mapping requirements.

The conversions are written as ABAP code rules in the field mapping logic. We need to understand and document:

- When these conversion rules are executed during the Migration Cockpit data load process
- How these conversions are triggered
- At which stage of the migration flow the converted values are applied
- Whether the execution behavior differs by migration object
- Any dependencies or prerequisites for these conversions to work correctly
- Can we automate these executions as part of Pre Validation API.

Migration consultants would be the right reference group to help clarify this behavior. We can connect with the consultants we have already reached out to earlier, or with any other known contacts who have experience with Migration Cockpit data loads and field mapping conversions.

Example Conversion:

For one of the field mappings, the Purchasing Document Type is determined based on the input value of BSTYP — Purchasing Document Category.

In this case, the ABAP conversion logic reads the input value for `BSTYP` and derives the appropriate Purchasing Document Type according to the rules written in the conversion.

Technical Name: Z_PUR_ORDER_2_M2V Generated

Header Data

- Legacy Purchasing Document Number
- Company Code
- Purchasing Document Type
- Supplier Account Number
- Purchasing Organization
- Purchasing Group
- Purchasing Document Date
- Terms of Payment Key
- Cash (Prompt Payment) Discount Days 1
- Cash (Prompt Payment) Discount Days 2

Target Structures

- Migration of Purchase Order Custom fields << S_EKKO
 - Start of Loop(S_EKKO) ()
 - Start of Record(HEADER<<S_EKKO) PLV BOR ()
 - End of Record(HEADER<<S_EKKO) PLV EOR ()
- Purchase Order Header Data << S_EKKO
 - Start of Record(R_IS_HEADER<<S_EKKO) BOR_EKKO ()
 - Purchasing Document Number SET_MM_PO_NUM(S_EKKO-EBELN)
 - Company Code CMT_BUKRS(S_EKKO-BUKRS)
 - Purchasing Document Type CMT_BSART('F', S_EKKO-BSART)
 - Deletion Indicator in Purchasing Document

Display Rule

Target Structure

Name	Purchase Order Header Data
Target Field	Purchasing Document Type

Rule

Name: CMT_BSART
Description: Conversion of Purchasing Document Type

Import Parameter

Parameter	Parameter Value	Description
IV_BSTYP	'F'	
IV_BSART	S_EKKO-BSART	Header Data-Purchasing Document Type

Display Rule Conversion of Purchasing Document Type

Rule Name: Conversion of Purchasing Document Type
Status: Released

Definition | Assignments

Parameter Definition

Parameter Type	Parameter Name	Parameter Typing	Associated Type	Parameter Description
Import Parameter	IV_BSTYP	TYPE	ANY	
Import Parameter	IV_BSART	TYPE	ANY	
Export Parameter	EV_BSART	TYPE	ANY	

Properties

Rule is based on: Source Code Display

Open Editor | Syntax Check | Pretty Printer

```

1 DATA:
2   lv_new_doc_category TYPE ebstyp.
3
4 IF NOT iv_bsart IS INITIAL.           "ignore initial value
5 IF iv_bstyp IS INITIAL.
6
7   PERFORM rule_allog_msg_p
8   USING
9     'E' 'CNV_DMC_SIN' '107'
10      'CMT_BSART'
11      iv_bsart
12      space
13      space
14      'IL'.

```

| ABAP | Ln 1 Col 1

Conversion example 2:

In this case, the ABAP conversion logic reads the input value for Our reference and sets the value for same field according to the rules written in the conversion.

Display Rule

Target Structure

Name

Purchase Order Header Data

Target Field

Our Reference

Rule

Name

SET_OUR_REF_2

Description

Set Our Reference

Import Parameter

Parameter	Parameter Value	Description
IV_UNSEZ	S_EKKO-UNSEZ	Header Data-Our Reference
IV_EBELN	S_EKKO-EBELN	Header Data-Legacy Purchasing Document Number

Sales Person

Telephone

Your Reference

Our Reference

Header Address (not allowed)

Collective Number

Different Invoicing Party

Our Reference

Logical System

Item Number Interval for Subitems

SET_OUR_REF_2 (S_EKKO-UNSEZ, S_EKKO-EBELN)

Display Rule Set Our Reference

Rule Name

Set Our Reference

Status

Released

Definition

Assignments

Parameter Definition

Parameter Type	Parameter Name	Parameter Typing	Associated Type	Parameter Description
Import Parameter	IV_UNSEZ	TYPE	ANY	
Import Parameter	IV_EBELN	TYPE	ANY	
Export Parameter	EV_UNSEZ	TYPE	ANY	

Properties

Rule is based on:

Source Code

Display

Open Editor

Syntax Check

Pretty Printer

13

IF iv_unsez IS NOT INITIAL.

ev_unsez = iv_unsez.

ELSE.

ev_unsez = iv_ebeln.

ENDIF.

about:blank?windowId=SecondaryReadingPane4

3/3