

Team members

Hatem Mahmoud

Abdelmoneim Samir

Alaa Atef

Ali Alaa

Under supervision of

Prof.Ibrahim Gomaa

Eng.Ahmed Ashraf




Scenario 7

City Bank Branch

Protect the Internet-facing banking portal while keeping the core banking database absolutely unreachable from the public Internet. Balance public accessibility with strict internal isolation and operational continuity.



Topology Architecture



Firewall Network Interfaces (GUI)

Huawei Bank-FW

Not secure | https://192.168.0.1:8443/default.html

Current User: admin | Commit | Save | Help | About | Change Password | Logout

HUAWEI

Huawei

USG6000V1-ENSP

Dashboard

Monitor

Policy

Object

Network

System

Interface

Link Interface

Link Interface Group

Interface Pair

Zone

VXLAN

DNS

DHCP Server

Route

IPSec

L2TP

L2TP over IPSec

GRE

SSL VPN

SACG

Interface List

+

 Add

-

 Delete

Refresh

Interface Name

Enter an interface name.

Search

Clear Search Condition

Interface Name	Zone	IP Address	Connection Type	VLAN/VXLAN	Mode	State			Enable	Edit
						Physical	IPv4	IPv6		
GE0/0/0(GE0/METH)	trust (default)	192.168.0.1	Static IP (IPv4)		Routing				☒	
GE1/0/0	untrust (public)	200.1.1.1	Static IP (IPv4)		Routing				☒	
GE1/0/1	ZTELLER (public)	192.168.10.1	Static IP (IPv4)		Routing				☒	
GE1/0/2	ZBACKOFFICE (public)	192.168.20.1	Static IP (IPv4)		Routing				☒	
GE1/0/3	ZATM (public)	192.168.30.1	Static IP (IPv4)		Routing				☒	
GE1/0/4	ZCUSTWIFI (public)	192.168.40.1	Static IP (IPv4)		Routing				☒	
GE1/0/5	ZDMZ (public)	192.168.50.1	Static IP (IPv4)		Routing				☒	
GE1/0/6	ZOCTV (public)	192.168.60.1	Static IP (IPv4)		Routing				☒	
Virtual-#0	-- NONE -- (public)		Static IP (IPv6)							


Page 1 of 1 | Records per page 50 | Displaying 1 - 9 of 9

CLI Console

Copyright © Huawei Technologies Co., Ltd. 2014-2018. All rights reserved.

10:38 PM
9/14/2025

Firewall Security Policies (GUI)



Security Zone

Huawei Bank-FW

Not secure | https://192.168.0.1:8443/default.html

Current User: admin | Commit | Save | Help | About | Change Password | Logout

Huawei

USG6000V1-ENSP

Dashboard

Monitor

Policy

Object

Network

System

Interface

Link Interface

Link Interface Group

Interface Pair

Zone

VLAN

DNS

DHCP Server

Route

IPSec

L2TP

L2TP over IPSec

GRE

SSL VPN

SACG

Zone List

Refresh

Enter a zone name.

Search

Clear Search Condition

Zone Name	Priority	Description	Number of Interfaces	Edit
local	100		0	
trust	85		1	
untrust	5		1	
dmz	50		0	
ZTELLER	84		1	
ZBACKOFFICE	80		1	
ZATM	60		1	
ZCUSTWIFI	10		1	
ZDMZ	49		1	
ZCCTV	20		1	

Page 1 of 1 | Records per page 50 | Displaying 1 - 10 of 10

CLI Console

Copyright © Huawei Technologies Co., Ltd. 2014-2018. All rights reserved.

11:19 PM
9/14/2025

NAT Policy

Security Policy

Security Policy

NAT Policy

NAT Policy

Server Mapping

Server Load Balancing

Bandwidth Management

Quota Control Policy

Proxy Policy

Security Protection

ASPF Configuration

NAT Policy

Source Translation Address Pool

Destination Translation Address Pool

NAT Policy List

+

Add

✖

Delete

📄

Copy

↔

Move

+

Insert

🔄

Reset All Statistics

🟢

Enable

🔴

Disable

Enter a keyword.

+

Add Filter

☐	Name	Description	Tag	NAT Type	NAT Mode	Schedule	Source Zone	Destination Zone/Outbound Interface	Source Address	Destination Address	Service
☐	bo_internet			NAT	Source address translation	any	ZBACKOFFICE	untrust	192.168.20.0/255.255.255.0	any	any
☐	custwifi_internet			NAT	Source address translation	any	ZCUSTWIFI	untrust	192.168.40.0/255.255.255.0	any	any
☒	default	This is the default rule		No translation	No translation	any	any	any	any	any	any

Page 1 of 1

Records per page 50


Displaying 1 - 3 of 3

CLI Console

Copyright © Huawei Technologies Co., Ltd.2014-2018 . All rights reserved.

10:38 PM
9/14/2025

Cloud Topology



Firewall Network Interface

Interface

Interface

Zone

Route

Static Route

IPSec

IPSec

Monitor

SSL VPN

SSL VPN

Interface

Network > Interface

Add

Refresh

Search

Interface	IP Address	Security Zone	Status	Access Management	
GigabitEthernet0/0/0	192.168.0.1/255.255.255.0	—	Up	ping, http, https, ssh, telnet	
GigabitEthernet1/0/0	200.1.1.1/255.255.255.0	untrust	Up	ping	
GigabitEthernet1/0/1	192.168.10.1/255.255.255.0	Z-TELLER	Up	ping	
GigabitEthernet1/0/2	192.168.20.1/255.255.255.0	Z-BACKOFFICE	Up	ping	
GigabitEthernet1/0/3	192.168.30.1/255.255.255.0	Z-ATM	Up	ping	
GigabitEthernet1/0/4	192.168.40.1/255.255.255.0	Z-CUSTWIFI	Up	ping	
GigabitEthernet1/0/5	192.168.50.1/255.255.255.0	Z-DMZ	Up	ping	
GigabitEthernet1/0/6	192.168.60.1/255.255.255.0	Z-CCTV	Up	ping	

8 items

New interfaces appear automatically when first configured; this page edits addressing, zone membership, and access management (service-manage).

Firewall Security Policy

Security Policy

Policy > Security Policy > Security Policy

+ Add

Delete

Refresh

Search

Name	Source Zone	Destination Zone	Source Address	Destination Address	User	User Group	Service	URL Category	Schedule	Content Security	Logs	Action
☐ inbound_webbank	untrust	Z-DMZ	any	192.168.50.10/255.255.255.255	any	any	http, https	any	—	—	—	permit
☐ deny_internet_other	untrust	any	any	any	any	any	any	any	—	—	traffic, policy, session	deny
☐ teller_to_db	Z-TELLER	Z-DMZ	any	192.168.50.11/255.255.255.255	any	any	DB_1521	any	—	—	—	permit
☐ deny_teller_internet	Z-TELLER	untrust	any	any	any	any	any	any	—	—	traffic, policy, session	deny
☐ deny_teller_other	Z-TELLER	any	any	any	any	any	any	any	—	—	traffic, policy, session	deny
☐ bo_to_web	Z-BACKOFFICE	Z-DMZ	any	192.168.50.10/255.255.255.255	any	any	http, https	any	—	—	—	permit
☐ bo_to_db	Z-BACKOFFICE	Z-DMZ	any	192.168.50.11/255.255.255.255	any	any	any	any	—	—	—	permit
☐ bo_to_ftp	Z-BACKOFFICE	Z-DMZ	any	192.168.50.12/255.255.255.255	any	any	ftp	any	—	—	—	permit
☐ bo_to_internet	Z-BACKOFFICE	untrust	any	any	any	any	any	any	—	—	—	permit
☐ atm_to_db	Z-ATM	Z-DMZ	any	192.168.50.11/255.255.255.255	any	any	DB_1521	any	—	—	—	permit
☐ deny_atm_other	Z-ATM	any	any	any	any	any	any	any	—	—	traffic, policy, session	deny
☐ custwifi_to_internet	Z-CUSTWIFI	untrust	any	any	any	any	any	any	—	—	—	permit
☐ deny_custwifi_internal	Z-CUSTWIFI	any	any	any	any	any	any	any	—	—	traffic, policy, session	deny
☐ bo_to_cctv	Z-BACKOFFICE	Z-CCTV	any	any	any	any	any	any	—	—	—	permit
☐ deny_cctv_any	Z-CCTV	any	any	any	any	any	any	any	—	—	traffic, policy, session	deny
☐ deny_dmz_internet	Z-DMZ	untrust	any	any	any	any	any	any	—	—	traffic, policy, session	deny
☐ default_deny	any	any	any	any	any	any	any	any	—	—	traffic, policy, session	deny
default	any	any	any	any	any	any	any	—	—	—	—	deny

17 items

Nat Policy

NAT Policy

Policy > NAT Policy

NAT Policy

Source Translation Address Pool

Server Mapping

FTP ALG (detect ftp)...

+
Add

Delete

Refresh

Search

Name	Source Zone	Destination Zone	Translation
☐ bo_internet	any	untrust	easy-ip
☐ custwifi_internet	any	untrust	easy-ip

2 items

Security Zones

Zone List

Network > Zone

+

Add

Delete

Refresh

Search

Zone Name	Priority	Description	Number of Interfaces	Member Interfaces
local	100		0	—
trust	85		0	—
dmz	50		0	—
untrust	5		1	GigabitEthernet1/0/0
☐ Z-TELLER	84		1	GigabitEthernet1/0/1
☐ Z-BACKOFFICE	80		1	GigabitEthernet1/0/2
☐ Z-ATM	60		1	GigabitEthernet1/0/3
☐ Z-CUSTWIFI	10		1	GigabitEthernet1/0/4
☐ Z-DMZ	49		1	GigabitEthernet1/0/5
☐ Z-CCTV	20		1	GigabitEthernet1/0/6

10 items

IP Address

NAT Server (Virtual IP): 200.1.1.10 → 192.168.50.10

R-Internet: 200.1.1.100 | R-Attacker: 200.1.1.200

FW: GE1/0/0 = 200.1.1.1

GE1/0/1+6 = 192.168.[10..60].1

GE0/0/0 = Mgmt

TELLER	LSW7: PC7	192.168.10.10	[DB access only]
BACKOFF	LSW6: R-BO	192.168.20.10	[FTP client]
ATM	LSW4: PC4	192.168.30.10	[DB access only]
CUSTWIFI	LSW3: PC3	192.168.40.10	[Internet only]
DMZ	LSW2: WEB	.50.10 DB .50.11 FTP .50.12	
CCTV	LSW5: PC5	192.168.60.10	[Isolated]

Detailed Firewall Interface Configuration

Below are the specific IP addresses and zones assigned to each network interface on the firewall, detailing their connections within the City Bank Branch network.

Interface	IP Address / Mask	Zone	Connected To
GE1/0/0	200.1.1.1 /24	untrust	LSW1 (Internet)
GE1/0/1	192.168.10.1 /24	ZTELLER	LSW7
GE1/0/2	192.168.20.1 /24	ZBACKOFFICE	LSW6
GE1/0/3	192.168.30.1 /24	ZATM	LSW4
GE1/0/4	192.168.40.1 /24	ZCUSTWIFI	LSW3
GE1/0/5	192.168.50.1 /24	ZDMZ	LSW2
GE1/0/6	192.168.60.1 /24	ZCCTV	LSW5

Thanks