# Thermoacoustic heat pumps

Thomas Meylaers April 2023

### ${\bf Abstract}$

## Contents

1	Introduction	4
2	Working principles  2.1 Standing Waves <sup>1-3</sup> 2.1.1 Efficiency and losses  2.2 Travelling Waves	5
3	Applications	6
4	Future challenges and limitations	6
5	Conclusion	6

### 1 Introduction

Thermoacoustic heat pumps (TAHP) are a new and upcoming technology. This technology offers an environment-friendly and efficient solution for heating applications.

In contrast to traditional heating and cooling applications which rely on the vapor compression cycles, TAHP uses the energy stored in sound waves to transfer heat between temperature reservoirs. These mechanisms have a relatively simple design compared to their more-traditional counterparts. TAHP also use more environment-friendly working media such as helium and hydrogen. Working on these principles, this technology has the potential to offer significant advantages over traditional heating and cooling methods, including reduced energy consumption, lower maintenance costs, and reduced environmental impact.<sup>1</sup>

This paper will first discuss the physics behind these systems in section X. Section X discusses the applications of TAHP with the difference between standing wave and traveling wave principles in mind. Subsequently, section X discusses the challenges and possible shortcomings of TAHP. This paper will conclude in section X with final remarks.

## 2 Working principles

## 2.1 Standing Waves $^{1-3}$

In a standing wave, gas parcels alternatively compress and expand. This process happens adiabatically. These compressions and expansions change the temperature and pressure of these gas parcels. When the pressure reaches maximum so does the temperature and vice versa.

These temperature variations are relatively small. For sounds at  $120 \ dB$ , the temperature oscillates up and down by only about 0.02 degrees Celcius. Most air conditioners and refrigerators need to pump heat over a range of 20 degrees or more. So the temperature changes within the gas are too small to be useful.

To handle larger temperature ranges TAHP put the gas in contact with a solid. A solid has a much higher heat capacity per unit volume than gas and can absorb a considerable amount more heat without changing temperature very much. The solid absorbs heat when a gas parcel compresses and moves to the left. The solid will release heat to a gas parcel when it drops in temperature due to expansion and moves to the right. A temperature gradient is created along the solid. The temperature gradient due to this gas parcel is very small, but when multiple of these gas parcels are all undergoing this process, they work as a sort of bucket brigade bringing heat from one side to the other. This cycle for a gas parcel plotted in a p-V diagram shows that there is work absorbed by the gas and is typical for a heat pump. This process can be reversed where a temperature gradient along the solid is provided by an outside source which

is then converted into acoustic power. Such a device is called a *thermoacoustic* heat engine or primer mover.

The solid used in TAHP should have good thermal contact when the parcel is stationary but poor thermal contact when the parcel is moving. The solid should not conduct heat from one end to the other and thus have a low conductivity. The quest of finding this material is a large part of making TAHP commercially viable, but plastic is often sufficient for experimental applications.

TAHP use a stack of plates of the solid previously discussed called the *stack*. These plates are mounted parallel to each other. Detailed analysis shows that the optimal distance between these plates is about four times the *thermal penetration depth*  $\delta_{\kappa} = \sqrt{\kappa/\pi f \rho c_p}$ .

The most rudimentary form of a TAHP consists of a resonator, gas, stack, acoustic transducer, and hot and cold heat exchangers. The acoustic transducer applies acoustic power W to the gas in the resonator such that a standing wave of the first harmonic is formed in the resonator. A stack is located at about a fourth of the resonator length from the transducer. A hot heat exchanger is mounted on the left at the side of the stack which is closest to the node where temperature and pressure will be at their maximum. A cold heat exchanger is then mounted on the right side closest to the anti-node.

The gasses used in TAHP are typically noble gasses such as helium, neon, argon, or a mixture of these gases. These gasses are used because they have low molecular weights and are highly compressible, which makes them ideal for use in thermoacoustic refrigerators. Additionally, they have low thermal conductivity, which helps to minimize heat transfer between the hot and cold sides of the device.

The bucket brigade of gas parcels pumps heat from the cold end of the stack to the hot end and creates a temperature gradient. In the case of a thermoacoustic refrigerator, the cold exchanger is connected to a room to be cooled at  $T_c$ , and the hot exchanger is connected to a heat sink at  $T_h$ . This is reversed when the desired effect is the heating of a room. This technology is, however, the most promising in the former case.

#### 2.1.1 Efficiency and losses

The efficiency for heat pumps, known as the coefficient of performance (COP), is limited by the second law of thermodynamics and is defined by the Carnot efficiency  $T_c/(T_h-T_c)$ . The losses preventing this device from reaching Carnot efficiency are as follows:

Inherent losses Inherent losses are due to the irreversibility of the heat transfer between the stack and a gas parcel. Because the heat transfer happens across a non-zero temperature difference  $\delta T$ , the entropy of the universe increases.

Viscous losses Viscous losses occur because the gas must overcome viscous shear forces in the stack. The viscous penetration depth  $\delta_{\mu} = \sqrt{\mu/\pi f \rho}$  is comparable to the thermal penetration depth  $\delta_{\kappa}$ . Because the plates are

spaced about four times this depth apart, the gasses undergo a significant amount of viscous shear.

- **Conduction losses** This loss occurs by the simple conduction of the hot end of the stack to the cold end of the stack.
- Auxiliary losses The losses discussed also happen in other parts of the device. Viscous and inherent losses also occur in other parts of the resonator, not necessarily in the stack, which also contributes to the losses. Conduction losses also occur through the casing of the resonator.
- **Transduction Losses** The acoustic transducer generating power for the system is also imperfect. In the case of an electrical system, i.e. a loud-speaker, the main losses will be Joule heating in the copper wires of the loudspeaker.

These losses combined cause simple standing-wave TAHP to be inefficient. A stereo configuration developed by Garrett<sup>1</sup> and his colleagues for the US Navy to cool radar electronics only achieved 17% of the Carnot efficiency. The refrigerator itself, however, achieved 26% of the maximum which is only half of what conventional cooling systems of similar shape can achieve.

#### 2.2 Travelling Waves

- 3 Applications
- 4 Future challenges and limitations
- 5 Conclusion

#### References

- $^{1}$  Steven Garrett and Scott Backhaus. The power of sound. American Scientist, 88, 11 2000.
- $^2$  Gregory W. Swift. Thermoacoustic Engines and Refrigerators. *Physics Today*,  $48(7):22{-}28,\ 07\ 1995.$
- <sup>3</sup> M.E.H. Tijani. Loudspeaker-driven thermo-acoustic refrigeration. 01 2001.