

Sudoku Question PDF Import — Sample

Machine-readable text format • One question per page • No OCR required

Recommended import contract

Rule	Specification
Question boundary	Exactly ONE question per PDF page
Field order	Always use the same order shown below
Field labels	Use the exact labels: ID, TYPE, DIFFICULTY, SCORE, CATEGORY_ID, INITIAL_GRID, SOLUTION_GRID
Grid format	Exactly 9 lines × 9 digits; 0 represents an empty cell
Grid characters	Only digits 0–9; no spaces, commas, or decorative symbols
ID	UUID; if omitted in future files, backend may generate it
Score	Integer
Blank lines	Allowed only between sections; parser should ignore surrounding whitespace

Important: The visible layout is intentionally simple. The real value is the fixed text structure, so the extractor can parse the PDF deterministically rather than relying on visual positioning.

Example page structure: metadata fields first, then INITIAL_GRID, then SOLUTION_GRID. Repeat this exact structure for every question.

QUESTION 001

Copy this page format exactly for every question in an import PDF.

ID	de112679-d081-4ace-8158-7a0e39257065
TYPE	INDIVIDUAL
DIFFICULTY	EASY
SCORE	100
CATEGORY_ID	550e8400-e29b-41d4-a716-446655440000

INITIAL_GRID

530070000
600195000
098000060
800060003
400803001
700020006
060000280
000419005
000080079

SOLUTION_GRID

534678912
672195348
198342567
859761423
426853791
713924856
961537284
287419635
345286179

Parser expectation: Read the nine lines immediately after INITIAL_GRID as the starting grid, and the nine lines immediately after SOLUTION_GRID as the complete solution.

QUESTION 002

Copy this page format exactly for every question in an import PDF.

ID	87377d04-7643-43f5-ae06-c7161576409d
TYPE	TEAM
DIFFICULTY	MEDIUM
SCORE	150
CATEGORY_ID	550e8400-e29b-41d4-a716-446655440001

INITIAL_GRID

003020600
900305001
001806400
008102900
700000008
006708200
002609500
800203009
005010300

SOLUTION_GRID

483921657
967345821
251876493
548132976
729564138
136798245
372689514
814253769
695417382

Parser expectation: Read the nine lines immediately after INITIAL_GRID as the starting grid, and the nine lines immediately after SOLUTION_GRID as the complete solution.