CONNECTICUT
Local Flyer Ads
FLYER · PRINT · MAGAZINE · DIGITAL

Screen Install Checklist

Digital Screen Ad Network

Bring: prepared tablet, wall charger, 6 ft+ cable (right angle plug if framed), mount or enclosure, cable clips, phone signed in to the dashboard, maintenance PIN, business cards or sticker.
Before you leave: the loop for this screen is built and its ads are **approved**.

1 Pick the spot (with the owner)

- [ ] Where customers wait or stand in line, at eye level (center about 5 ft up), in **portrait**.
- [ ] Within cable reach of an outlet that is **always on**: not on a light switch, not on a power strip turned off at closing.
- [ ] No direct sun or glare on the screen. Away from sinks, heat and doorways people brush past.
- [ ] Good WiFi there: check the bars on your phone in that exact spot.
- [ ] Doesn't block exits, signs or the owner's displays. The owner says yes to the spot.

2 Mount and power

- [ ] Mount firmly (locking enclosure, wall mount or strong adhesive frame), **portrait**, charging port reachable.
- [ ] Cover or hide the power and volume buttons if the mount allows.
- [ ] Route the cable along edges and clip it down, no loops. Plug in and confirm the charging icon on the dashboard.

3 WiFi

- [ ] Ask for the **guest WiFi** name and password. It must not need a sign in page (hotel or café style login).
- [ ] On the tablet: tap corners clockwise from top left, enter PIN, tap **Exit kiosk for 15 min**. Connect to WiFi, press **Home**, then **Back to kiosk mode now**.
- [ ] Write the network name in the screen's address notes on the dashboard.

4 Pair and check (on your phone)

- [ ] Not paired yet? **Screens, then Pair new screen**: enter the tablet's code, screen name, venue, address and loop.
- [ ] Within a minute the dashboard shows **online**, **in sync** and **charging**, on the map at the right place.
- [ ] Watch one full loop: every ad shows, upright, no black screens.
- [ ] Brightness up, sound as the owner prefers. Then press Home, swipe the edges, press power once: it must stay on the ads.

5 Tell the owner

- “It runs by itself. It turns on, updates and restarts on its own. You never need to touch it.”
- “Please keep it **plugged in** and don't move or cover it. If the power goes out, it comes back on its own.”
- “If it's ever black, check that it's plugged in and the WiFi works. If you change the WiFi password, call me.”
- “We monitor it remotely and get an alert if it goes offline, so we may call or stop by.”
- “Customers who ask about advertising on it: here's my card.” Leave your card or sticker by the screen.

6 Before you go

- [ ] Take a photo of the installed screen. Save the owner's name, phone and install date in the dashboard notes.
- [ ] Check the dashboard once more from the parking lot: still online and playing.

Business: _____ Date: _____

Owner name and phone: _____ Screen name: _____

WiFi network: _____ Notes: _____