

EEE 154

Engineering Drawing

Course Instructor :

Mohammad Sabbir Rahman

Assistant Professor

Department of Civil Engineering

University of Asia Pacific

& Senior Lecturer


Electrical and Computer Engineering

North-South University

Mobile: +8801734082514

Email: sabbir.rahman01@northsouth.edu


Dimension Style Manager : D+enter



1. Modify

12. Set Current

13. Close




2. Symbols and Arrow tab

3. Arrow Size


4. Center Mark

5. Beak Size



6. Text Tab

7. Text height




8. Primary Units Tab

9. Arrow Symbol


10. Arrow Size

11. OK

Multi leader Style : MLS+enter




1. Modify



2. Content

3. Text Height



4. Leader format

5. Arrow Symbol


6. Arrow Size

7. Break Size

8. OK

Object Snap: OS+enter

1. **Select all**
2. **OK**



Dynamic Input ON/Off : F12 +Enter

1. Press the F12 key to toggle Dynamic Input on and off.

Ribbon On/Off:




1. **Ribbon (on)**
2. **Ribbon-close (off)**

Regular Selection box:

1. **Pickauto**
2. **Value: 3**

Layer : LA+enter

1. Alt+N (New layer)
2. Alt+D (delete layer)



1. F2 for
Rename layer

2. Click bulb/Sun for
hiding the layer

3. Click Lock to
lock the layer



Click color to
change the color

Line weight

i. Click line type to change type of line

iii. Select the line type

iv. OK



ii. Load



Orthographic Line:

L+enter

1. Press F8 to on the orthographic mode
2. Click starting point of line
3. move the mouse to direction of supposed to draw a line
4. Type the line length (mm or inch)
5. Enter + enter

Poly Line (continuous line)

: PL+enter

1. Press F8 to on the orthographic mode
2. Click starting point of line
3. move the mouse to direction of supposed to draw a line
4. Type the line length (mm or inch)
5. Enter
6. Repeat and reapeat
7. Enter + enter

On/Off of orthographic mode

Press F8 to on or off

Circle: C+enter

1. Click center of circle
2. Move mouse in any direction
3. D (diameter) or R(radius) +enter
4. Type D or R value +enter

Arc: ARC+enter

1. Click starting point
2. Click 2nd point
3. Click 3rd point
4. Adjust the ARC by mouse click and stretching

Rectangular object:

REC+enter

1. Click left (bottom) corner of Rectangle
2. Move mouse upward and right direction
3. type: @ 25 (horizontal) ,20 (Vertical)
4. Enter




Hatch: HA+enter

1. Click in enclosed area (Supposed to fill with a pattern)
2. Select Pattern
3. Adjust the pattern scale , angle and Transparency
4. Close Hatch


On/Off of orthographic mode

Press F8 to on or off

Polygon(triangle, quadrilateral, pentagons, hexagon, heptagon (or septagon), octagon, etc) : POL+enter



Inscribe in a circle



Circumscribe

1. Number of side (Ex: 5)
2. Click center of polygon (**inscribe in circle or Circumscribe**)
3. Type radius of circle
4. Enter


Move: M+enter

1. *Select object +enter*
2. *Click 1st reference point*
3. *Move the object and click 2nd reference point*

Copy: CO+enter

1. *Select object +enter*
2. *Click 1st reference point*
3. *Move the object and click 2nd reference point*

STRETCH: S+enter

- 
1. *Select face (supposed to stretch)*
 2. *Click 1st and 2nd point*
 3. *Move the face to direction of stretch*
 4. *Type value of stretch*
 5. *Enter*

On/Off of orthographic mode


Press F8 to on or off

Scale: SC+enter

1. *Select object + enter*
2. *Click center any point of object*
3. *Type Scale value*
4. *Enter*

Mirror: MI+enter

1. *Select object + enter*
2. *Click Reference two points (Horizontal or vertical two points) to mirror the object*
3. *Enter*



Trim:


1. Select object
2. **TR+enter**
3. Click Object to trim

Spline


1. **SPL+Enter**
2. Click more and more to get desire line



Fillet :F+enter




1. **R+enter+0 (zero)+enter**
2. Click two lines



1. **R + enter + value(arc radius value)+enter**
2. Click two lines


Chamfer: CHA+enter

1. **D + enter**
2. Type first line chamfer value
3. Type 2nd line chamfer value
4. Click two lines




Join: J+enter

1. Select object + enter



EXPLODE : X+enter


1. Select object + enter



Erase:

1. Select object + Delete key **or**
2. **E+enter+Select object+enter**

Offset :O+enter



Offset direction

1. Offset value (10) +enter
2. Click line
3. Move mouse to direction of offset
4. Click again
5. 2nd offset (Click previous line and click again to offset ; **Hence same offset of 1st line**)
6. 3rd offset (double enter + offset value (12) +click two times)


Extend :

1. Set boundary to limit the extend
2. **EX+enter**
3. Click object to extend

Boundary

Divide:

1. **ddtype(ptype) + enter +select a icon + OK**
2. **div+enter**
3. Select object
4. Number of segment (3)+enter




Text:T+enter

1. Click left (bottom) corner
2. Move mouse upward and right direction
3. Click +Type the text
4. Select all text + type the text height +front type +enter +Close text editor

Select all text




Text Size



ARRAY


Rectangular Array

1. Select object
2. AR+ enter
3. R+ Enter




Path Array:

1. draw path for path array
2. Select object
3. AR+enter
4. PA+Enter
5. Select path for array



Polar Array:


1. Draw a circle
2. Select object
3. AR+enter
4. PO+Enter
5. Click the center of a circle






Dimensions

1. Click here to get desire dimension type
2. Apply it



Leader

1. Click here to get desire leader type
2. Apply it



Column

Row

Width

Height

Table

1. Table +enter
2. Modify all data
3. OK

<https://www.javatpoint.com/autocad-dynamic-input>