

CORNE CHOC PRO

TRAVIS · MACOS · VIM · CAGS

tap / hold appears as two lines · ▽ Base passthrough · ✕ disabled
Shot macOS selection screenshot · Function + B enters the bootloader

BASE

QWERTY · mirrored CAGS

Tab	Q	W	E	R	T	Y	U	I	O	P	Del
Esc hold Nav	A hold Ctrl	S hold Opt	D hold Cmd	F hold Shift	G	H	J hold Shift	K hold Cmd	L hold Opt	;	'
Shift	Z	X	C	V	B	N	M	,	.	/	Fn
1x Ctrl Enter hold Cmd Tab hold Raise Bsp hold Nav Space 1x Shift											

Home row: A/S/D/F = Ctrl/Opt/Cmd/Shift; mirrored on J/K/L/;. Tap Caps-position for Escape.

RAISE

hold left Tab / Raise thumb

~	!	@	#	\$	%	=	7	8	9	-	Shot
`	(	)	[	]	\	*	4	5	6	+	Enter
_	<	>	{	}		0	1	2	3	.	/
▽ ▽ Raise ▽ ▽ :											

Left: adjacent delimiter pairs. Right: 789 / 456 / 123 numpad. Shot sends ⌘⇧4; thumb Backspace remains available.

NAVIGATE

hold Esc / Nav or Bsp / Nav

▽	⌘1	⌘2	⌘3	⌘4	⌘5	PrevTab	NextTab	Close	Reopen	Window	▽
▽	Line ←	Line →	Word ←	Word →	PgDn	←	↓	↑	→	AppSwitch	▽
▽	Undo	Redo	Copy	Paste	Cut	Play	Prev	Next	Vol-	Vol+	▽
▽ ▽ ▽ Nav ▽ ▽											

Vim position: physical H/J/K/L become ←/↓/↑/→. macOS line, word, tab, app, window, edit, and media actions.

FUNCTION

tap or hold bottom-right Function

F1	F2	F3	F4	F5	F6	F7	F8	F9	F10	F11	F12
RGB	Bright +	Bright -	CapsWord	✕	✕	✕	✕	✕	✕	✕	✕
RGB Mode	✕	✕	✕	✕	Boot	✕	✕	✕	✕	✕	▽
▽ ▽ ▽ ▽ ▽ ▽											

Caps Word: Function + physical D. Boot: Function + physical B, opposite the activation key.