CARD 8 · FRONT · SIDE 1 OF 2

Council / Area EOC — Only When the Council or the Welfare Region Opens One

Share this card

WHEN IT EXISTS

There is no standing Area EOC. The coordinating council (Area Seventy) or the welfare region opens one when several stakes are hit, usually at the station of the Area Welfare and Self-Reliance Specialist (often a HAM, amateur radio operator, who works both the council line and the welfare line).

Until then each Stake EOC reports straight to the two lines above it, and this card is not in use.

SETUP TAB, ONCE

Level **Council / Area** · this EOC's name · the stakes it covers (**Save EOC Identity** puts them on the Roster) · its drop email and Winlink address, given to every Stake EOC on the comms sheet.

WHAT COMES IN

Each Stake EOC's **SITREP** (situation report) and **roll-up** (a JSON, JavaScript Object Notation, data file). Roll-ups by email or Winlink file themselves; from a USB (Universal Serial Bus) drive, drop the file in the Drop Folder. **Via** shows the Stake EOC.

Roster tab: which stakes have reported, which are overdue; totals across stakes on the wall display.

WHAT IT DOES

Supply Order totals by stake for the Area Welfare and Self-Reliance Manager (AWSRM) and the storehouse (water, blankets, cleaning kits; which stake center receives); record the approval on each order.

Answering a Supply Order: open the item → **Reply to <stake EOC>** → send the .json to that stake's drop email or Winlink address; their item closes DONE with your decision.

Headquarters assistance requests from the stakes, consolidated. Its own SITREP (every stake's totals) to the Area Presidency and Church headquarters, as directed, on the interval they set.

WORK ITEMS

Stake items marked **Up** arrive here open, named with the stake; give each an owner. Items from the welfare line (totals by a deadline) land only on the Council / Area EOC's list, not the stakes'.

IN A DRILL

The Area simulator plays the councils. Stakes nobody plays arrive as roll-up files at the SITREP times. New to drills? Card 9.

> **Card 3** runs the Message Center; start with its Overview checklist. This card: what your level does and owes the level above.

Turn over → Card 8, side 2: The Chain, the Roll-up Path, Phones and Drills

COUNCIL / AREA EOC (EMERGENCY OPERATIONS CENTER) — CARD 8 OF THE EOC SET

CARD 8 · BACK · SIDE 2 OF 2

The Chain, the Roll-up Path, Phones and Drills

THE CHAIN AT A GLANCE

EOC	Reports from	SITREP to	Roll-up JSON to
Satellite	its wards	Stake Center EOC	Stake Center EOC
Stake Center	wards + satellites	Stake President, council line, welfare line	Council / Area EOC, if open
Council / Area ◀ you	stakes	Area Presidency / Church headquarters, as directed	—

SITREP = situation report. The council line is the Area Seventy; the welfare line is the Welfare and Self-Reliance Manager (WSRM), then the Area Welfare and Self-Reliance Manager (AWSRM). A Council / Area EOC exists only when the council or the welfare region opens one.

ROLL-UP: HOW THE FILE TRAVELS

Setup tab → **Export Roll-up JSON** ("only new since last roll-up" ticked) → send it with every SITREP.

P / A (cellular, any internet): attach it to an email to the parent EOC's drop email. **C** (radio): attach it to a Winlink message to the parent's Winlink address. In order (VARA: the sound-card radio modem Winlink uses): RMS (Radio Message Server) Gateway, held at the gateway, VARA FM RMS Post Office, VARA FM P2P (peer-to-peer), then VARA HF. **E** (runner): on a USB drive with the printed SITREP.

The parent merges it by itself within 10 seconds ("Roll-up received from …"). From USB: drop it in the Drop Folder. Nothing counts twice.

> **Any device in the room, no app needed:** scan the wall QR (Quick Response) code (or open `http://<server-ip>:8080/m`): new reports, **Send to EOC**, the **Work items** list (tap an item: **Take it**, In work, Up, Done; your name goes in its log). **Paper by runner (Emergency):** type it in at `/forms/dr`, `/forms/so` or `/forms/wcl` and tap **Send**; keep blank paper forms on hand (add `?blank=1`, **Print**).

> **In a drill:** one simulator per EOC. The purple **drill bar** on every screen says what this EOC plays, the clock or the start time, and who is ready: press **I am ready**. Every simulated report says SIMULATED; real reports still go through. New to drills? Read **card 9**.

Church of Jesus Christ EMCOMM (emergency communications) is an independent volunteer project created by Travis Hilton (W9TLH), not an official product of The Church of Jesus Christ of Latter-day Saints.