CARD 7 · FRONT · SIDE 1 OF 2

Stake Center EOC — The Stake's Picture, Reporting to the Two Lines Above

Share this card

WHO DECIDES

The stake **Welfare and Self-Reliance Specialist (emergency communications)** recommends the PACE (Primary, Alternate, Contingency, Emergency) level and when to open a Satellite EOC; the **Stake President decides**; the ERD (Emergency Response Director) or the specialist announces it. Set the PACE level on the Setup tab the moment it changes and log the time.

SETUP TAB, ONCE

Level **Stake** · this EOC's name · parent = the two lines above the stake: the **council line** (Area Seventy; decisions) and the **welfare line** (the Welfare and Self-Reliance Manager, WSRM, then the Area Welfare and Self-Reliance Manager, AWSRM; supplies, approvals, reporting), or a **Council / Area EOC** when one is open · the SITREP (situation report) interval leadership set.

Comms sheet: every EOC's Winlink address, gateways in order, net frequencies; **Export sheet JSON** (JavaScript Object Notation, a data file) to every Satellite EOC.

WHAT COMES IN

Every ward not covered by a satellite (phones, Winlink, Drop Folder; USB (Universal Serial Bus) drives too) and each **Satellite EOC's roll-up** (merges itself; **Via** on the Messages tab shows which EOC it came through; nothing is counted twice).

Roster tab: wards and bishops, who has reported, who is overdue, missionaries not accounted for.

WHAT GOES UP, WITH EVERY SITREP

SITREP to the Stake President, the council line and the welfare line: first as soon as possible, then on the interval leadership set. PACE level in force in the header.

Supply Orders to the welfare line for approval; record the AWSRM's answer on the order. **Headquarters assistance** requests go up the same way.

Export Roll-up JSON only to a Council / Area EOC when one is open (back of this card). Otherwise the SITREP is the stake's report upward.

WORK ITEMS

The mission office, the county, the Stake President and the welfare line ask through this list; the reports add their own. Give every HIGH item an owner at once. **Up** = sent to the line above; write the **decision** when it comes back. The same list is on every phone in the room.

> **Card 3** is how to run the Message Center (start-up, auto-ingest, tabs, status, handoff). This card is what your level does and what it owes the level above.

Turn over → Card 7, side 2: The Chain, the Roll-up Path, Phones and Drills

STAKE CENTER EOC (EMERGENCY OPERATIONS CENTER) — CARD 7 OF THE EOC SET

CARD 7 · BACK · SIDE 2 OF 2

The Chain, the Roll-up Path, Phones and Drills

THE CHAIN AT A GLANCE

EOC	Reports from	SITREP to	Roll-up JSON to
Satellite	its wards	Stake Center EOC	Stake Center EOC
Stake Center ◀ you	wards + satellites	Stake President, council line, welfare line	Council / Area EOC, if open
Council / Area	stakes	Area Presidency / Church headquarters, as directed	—

SITREP = situation report. The council line is the Area Seventy; the welfare line is the Welfare and Self-Reliance Manager (WSRM), then the Area Welfare and Self-Reliance Manager (AWSRM). A Council / Area EOC exists only when the council or the welfare region opens one.

ROLL-UP: HOW THE FILE TRAVELS

Setup tab → **Export Roll-up JSON** ("only new since last roll-up" ticked) → send it with every SITREP.

P / A (cellular, any internet): attach it to an email to the parent EOC's drop email. **C** (radio): attach it to a Winlink message to the parent's Winlink address. First Winlink peer-to-peer (P2P) over VARA FM straight to a nearby parent station, then VARA FM through a gateway, then VARA HF (VARA: the sound-card radio modem Winlink uses). **E** (runner): on a USB drive with the printed SITREP.

At the parent nothing is clicked: the Drop Folder and Winlink watchers merge it within 10 seconds and log "Roll-up received from …". From USB: drop it in the Drop Folder. Nothing is counted twice.

> **Any device in the room, no app needed:** scan the wall QR (Quick Response) code (or open `http://<server-ip>:8080/m`): new reports, **Send to EOC**, the **Work items** list (tap an item: **Take it**, In work, Up, Done; your name goes in its log). **Paper by runner (Emergency):** type it in at `/forms/dr`, `/forms/so` or `/forms/wcl` and tap **Send**; keep blank paper forms on hand (add `?blank=1`, **Print**).

> **In a drill:** one simulator per EOC. The purple **drill bar** on every screen says what this EOC plays, the clock or the start time, and who is ready: press **I am ready**. Every simulated report says SIMULATED; real reports still go through. New to drills? Read **card 9**.

Church of Jesus Christ EMCOMM (emergency communications) is an independent volunteer project created by Travis Hilton (W9TLH), not an official product of The Church of Jesus Christ of Latter-day Saints.

travislhilton.github.io/church-emcomm-wnlk-forms/forms/