HELPING HANDS VOLUNTEER

CARD 1 · FRONT · SIDE 1 OF 2

Reporting Damage or Needs

Share this card

Safety first. Your family and yourself first. Never enter a damaged building. Then report.

SCAN TO START

OR GO TO THIS ADDRESS:

`travislhilton.github.io/church-emcomm-wnlk-forms/forms/`

The same QR (Quick Response) code is on posters at staging areas and sign-in tables. No account needed. Works on any phone.

1. **Scan the QR code** or go to the address. Tap your form.
   Disaster Report · Supply Order · Work Crew Log
2. **In a drill, tick THIS IS AN EXERCISE** at the top of the form.
3. **Fill in the form:** address, damage, people who need help.
   Allow location: your GPS (Global Positioning System) position fills in by itself. Box grayed out? Tap Enter coordinates manually.
4. **Tap Save to Outbox.** The report waits on your phone, even with no signal.
5. **Send it.** At the EOC (Emergency Operations Center), on its Wi-Fi: tap **Send to EOC** and scan the QR code on the wall. Anywhere else: the table below, top row first.
   iPhone: after the green receipt, switch back to the app and tap **Yes**.

NOT AT THE EOC? TRY P, THEN A, THEN C, THEN E

The PACE plan: Primary, Alternate, Contingency, Emergency.

P	Cell signal	Tap **Share by text or email**. Send it to your Team Leader or your Stake or Satellite EOC.
A	Any internet, anywhere	The same, over any Wi-Fi with internet: home, a shelter, a business, a meetinghouse, Starlink.
C	No internet	Find a HAM (amateur radio) operator. Tap **Save to My Phone** to make a file and give it to them on a USB (Universal Serial Bus) drive. Or carry your phone to the EOC Wi-Fi.
E	Nothing works	Paper by hand. Tap **Print** under the form, or fill in a blank paper form. Give it to your Crew Chief or a runner.

Turn over → Card 1, side 2: Before the Emergency — Do These Now

HELPING HANDS VOLUNTEER

CARD 1 · BACK · SIDE 2 OF 2

Before the Emergency — Do These Now

- ☐ Install the app now, with internet: iPhone Safari → Share → Add to Home Screen; Android Chrome → Install app. Open each form once. Forgot? At the EOC, scan the wall QR code: the forms work there with no app.
- ☐ Load your stake's Comms Sheet (portal → Comms sheet → Load sheet file). It holds the numbers and addresses to send to. It works with no signal.
- ☐ Fill in one practice form with your home address. Tick THIS IS AN EXERCISE. Tap Save to Outbox and check it is there.
- ☐ Print 3 blank copies of each form (portal → Paper forms). Keep them with a pen in your go-bag.

Direct Links — Each Form

Disaster Report
Damaged home, injuries, immediate needs

Supply Order
Food, equipment, or supplies needed

Work Crew Log
Crew hours & tasks (Crew Chief fills)

Not sure? Ask your Team Leader. A late report is better than none. A wrong number can be fixed: send a new report that says what changed.

Printing on paper (Emergency): the printer must be on your Wi-Fi, or offer its own Wi-Fi (Wi-Fi Direct): join it in Settings → Wi-Fi first. Keep the report in your Outbox too.

Something not working, or feedback after a drill? Tell your Team Leader or the stake specialist: the stake Welfare and Self-Reliance Specialist (emergency communications). Say what you did, what you saw, and which phone.

Church of Jesus Christ EMCOMM is an independent volunteer project created by Travis Hilton (W9TLH), not an official product of The Church of Jesus Christ of Latter-day Saints.

travislhilton.github.io/church-emcomm-wnlk-forms/forms/

EMCOMM (EMERGENCY COMMUNICATIONS) HAM (AMATEUR RADIO) OPERATOR

CARD 2 · FRONT · SIDE 1 OF 2

Sending a Church Form via Winlink

Share this card

A · CREATE THE FORM YOURSELF (report given by voice on the net, in person or on paper)

1. **Winlink Express → New Message → Select Template → Global Templates → Church of Jesus Christ EMCOMM Forms** → pick the form
   Disaster Report · Supply Order · Work Crew Log. To practice: …*EMCOMM Practice* has seven pre-filled exercise forms
2. **Fill in the form** that opens in your browser
   Drill or test? Tick **THIS IS AN EXERCISE** at the top. Your callsign and station fill in from Winlink. **Save Data** keeps a copy.
3. **Submit → address it to *your* EOC (Emergency Operations Center) → Open Session → Telnet**, or VARA FM / VARA HF (VARA: the radio modem Winlink uses) when the internet is down (back)
   Your Satellite or Stake Center EOC's Winlink address is on the stake Comms Sheet.
4. **Confirm** it is in Sent Items, then report on the net

B · SEND A FORM A VOLUNTEER FILLED IN (a .txt save file from the portal)

5. **Receive the .txt file** — text, email or USB (Universal Serial Bus) drive
6. **Step 1, then Load Data** → select the file → every field fills in. Review, then send as in steps 3–4
   Your callsign and station are never overwritten. No GPS (Global Positioning System) position in the file? Your station's fills in.

Key phrase up: "Stake EOC, this is [callsign], I have transmitted [N] forms via [PACE level]. Receipt confirmed."
PACE: Primary, Alternate, Contingency, Emergency.

Submit says "localhost refused"? Nothing was sent. Close every localhost:8001 tab and the message, Select Template again, Load Data, Submit. One form open at a time.

Before every event: Winlink Express (`winlink.org`) and VARA FM / VARA HF (`downloads.winlink.org/VARA Products/`) installed and tested · templates in `Global Folders\Templates\Church of Jesus Christ EMCOMM Forms\` · Telnet tested within 30 days · nearest RMS (Radio Message Server) gateway programmed (winlink.org/RMSChannels). Send a monthly test message, a different PACE level each month.

Turn over → Card 2, side 2: PACE Levels: Which Path, When to Step Down

EMCOMM HAM OPERATOR

CARD 2 · BACK · SIDE 2 OF 2

PACE Levels: Which Path, When to Step Down

PACE	Situation	Winlink Connection
P	Cell + internet up	Volunteers text/email files to the EOC. You: Open Session → **Telnet**
A	Cell down, any internet anywhere	Any connection that still reaches the internet. Files arrive by email or USB drive. Open Session → **Telnet**
C	No internet; a gateway answers	**Data:** Open Session → **Vara FM Winlink** → [pre-programmed VHF/UHF gateway freq] (very/ultra high frequency). Send as **Winlink Message**. A gateway with no internet may hold it for the CMS (Common Message Servers). **Voice:** stake VHF/UHF net (repeater, then simplex); volunteers on FRS/GMRS (Family Radio Service / General Mobile Radio Service) to Team Leaders.
C	"No CMS available" or no gateway	Wrong Send as stays in the Outbox. **1. Vara FM RMS Post Office**: Send as Post Office. **2. Vara FM P2P** (peer-to-peer): Send as Peer-to-Peer. Not forwarded: the recipient must connect. **3. Vara HF Winlink** (high frequency), 40m or 80m: only what must go. **iPhone reports:** a USB-C/Lightning thumb drive in the go-kit, or the EOC Wi-Fi **Send to EOC**.
E	Nothing connects, no one answers the net	**Runner:** the printed form, or a blank form filled by hand, to the EOC; the operator types it in. Hold saved files; send when any path returns.

Addresses, gateways, Post Office, P2P frequency, nets: from the stake **Comms Sheet** — printed copy in the go-bag, or load the sheet file on your phone at …/`forms/comms.html`.

PACE rule: step down a level after two failed attempts in 15 minutes, or when the Stake President decides it. Do not go back to a path that failed until a test message gets through. The stake Welfare and Self-Reliance Specialist (emergency communications) recommends the level, the Stake President decides, and the Emergency Response Director (ERD) or specialist announces it. The county may call ARES (Amateur Radio Emergency Service) operators to county duty at its Emergency level; agree beforehand who stays with the stake.

Church of Jesus Christ EMCOMM is an independent volunteer project created by Travis Hilton (W9TLH), not an official product of The Church of Jesus Christ of Latter-day Saints.

EOC OPERATOR — SATELLITE, STAKE CENTER OR COUNCIL / AREA EOC

CARD 3 · FRONT · SIDE 1 OF 2

Running the EOC (Emergency Operations Center) Message Center

Share this card

STARTING UP

1. **Double-click the EOC Server icon** on the Windows host laptop
   Window shows: `http://10.x.x.x:8080` — note this IP (Internet Protocol) address
2. **Share the URL (web address)** with the EOC operators on the Wi-Fi: any device, any browser. A green banner = networked.

RECEIVING MESSAGES

3. Open Winlink Express → check for new mail
   During an activation, set Telnet to check every 5 minutes.
4. **Watch the blue "AUTO-INGEST ACTIVE" bar** in the EOC
   Church forms appear on every screen within 10 seconds.
5. Once: **choose the Winlink callsign** that feeds the EOC
   Click the blue bar and type it (it lists the ones found). Auto-ingest off? Drag the .mime from C:\RMS Express\<callsign>\Messages onto the page.
6. **SITREP (situation report):** Disaster Reports tab → **Generate SITREP** (toolbar above the table) → **Copy** → send it up
   Satellite → Stake Center EOC. Stake → council line (Area Seventy) and welfare line: Welfare and Self-Reliance Manager (WSRM), then Area Welfare and Self-Reliance Manager (AWSRM).
7. **Stake EOC: forward the forms up the welfare line**
   Winlink Express: open the form message → Forward → the welfare line's Winlink address → Send. Every Disaster Report and Supply Order.

Every work item (Work Items tab): give it an owner now (HIGH items at once), move it (In work, Up, Done), and write the decision in.

Reports without Winlink. Phones: volunteers on the EOC Wi-Fi tap **Send to EOC** (the wall code). Other reports arrive as `.txt` files: save them into the **EOC Drop Folder** on the Desktop.

Paper by runner (Emergency): type it in at `http://<server-ip>:8080/forms/dr` (so, `wcl`) and tap **Send**.

Before the event: Python 3 from `python.org/downloads` (not the Microsoft Store placeholder) and Winlink Express · USB (Universal Serial Bus) thumb drives, one USB-C/Lightning for iPhones · **Comms Sheet** typed on the Setup tab; **Export sheet JSON** (JavaScript Object Notation file) to every EOC · blank paper forms (form address + `?blank=1`, **Print**).

Turn over → Card 3, side 2: Tabs, Status, Shift Handoff, Roll-up & SITREP

EOC OPERATOR — SATELLITE, STAKE CENTER OR COUNCIL / AREA EOC

CARD 3 · BACK · SIDE 2 OF 2

Tabs, Status, Shift Handoff, Roll-up & SITREP

TABS — WHAT GOES WHERE

Disaster Reports — per-address damage records
Supply Orders — requests + the welfare line's approval status
Work Crew Logs — crews, hours, homes completed
Roster — wards (stakes at a Council / Area EOC) and who has reported
Work Items — what the reports ask you to do or decide: owner, status, next action, decision
Messages — every record, **Via** = the EOC it came through · **Notes** — shift log

Status badges (click one to move it on; every screen updates): NEW just arrived, nobody has read it · ACK acknowledged: someone read it · ASSGN assigned: someone is acting on it · DONE handled.

Shift Handoff: Export Handoff JSON → USB drive → the incoming operator clicks Import Handoff JSON (it *replaces* the event's records: shift change only). **New emergency?** Setup tab → **Open a New Event** (the old event keeps its reports).

Roll-up to the EOC above you (Satellite → Stake → Council / Area EOC, if open): Setup tab: level, name and parent once → **Export Roll-up JSON** ("only new" ticked) with every SITREP, by the PACE (Primary, Alternate, Contingency, Emergency) level: **P/A** email to the parent's drop email · **C** Winlink attachment · **E** USB drive with the printed SITREP. The parent merges it by itself; nothing counts twice. **No Council / Area EOC open?** Items set Up go up only in the SITREP; phone or email the welfare line for anything urgent.

SITREP: first as soon as possible, then regular status reports on the interval leadership sets (Setup tab), to the Stake President, the council line (Area Seventy) and the welfare line (WSRM, AWSRM). Header: the **PACE level in force**; log each change with the time. Send by email at P/A, Winlink radio (VARA FM or VARA HF, the radio modem) at C, county EOC liaison or courier at E.

Wall display (TV): open `http://<server-ip>:8080/wall`, press **F**. **Drill:** press **I am ready** on the drill bar; new to drills: card 9. Your level: cards 6–8.

Church of Jesus Christ EMCOMM (emergency communications) is an independent volunteer project created by Travis Hilton (W9TLH), not an official product of The Church of Jesus Christ of Latter-day Saints.

travislhilton.github.io/church-emcomm-wnlk-forms/forms/

FOR BISHOPS, STAKE PRESIDENTS & EMERGENCY RESPONSE DIRECTORS

CARD 4 · FRONT · SIDE 1 OF 2

Church of Jesus Christ EMCOMM — How It Works

Share this card

EMCOMM (emergency communications): Helping Hands volunteers fill in the three Church forms on their phones. Phones, the internet or HAM (amateur radio) operators carry them to the Stake EOC (Emergency Operations Center) and the lines above, even when cell and internet are down.

HOW INFORMATION FLOWS

Volunteer fills form on phone → **Team Leader** collects, hands to HAM → **HAM Operator** radio or internet → **Stake EOC** tracks it all → **Council + welfare** Area Seventy; the welfare line

THE PACE PLAN — FOUR INDEPENDENT PATHS, USED IN ORDER

P	**Primary — cell**	Volunteers text or email the form file
A	**Alternate — any internet**	The same over any Wi-Fi that still has internet: home, shelter, business, meetinghouse, Starlink
C	**Contingency — radio**	HAM operators send forms by Winlink radio (VARA FM first, then VARA HF: the radio modems Winlink uses); voice on FRS/GMRS (Family Radio Service / General Mobile Radio Service) and the stake net
E	**Emergency — runner**	Paper form carried by hand: printed from the phone, or a blank form filled in

Matches the county ARES (Amateur Radio Emergency Service) plan where the stake sits.

Who decides: the stake **Welfare and Self-Reliance Specialist** (emergency communications) recommends the level, the **Stake President decides** (the bishop for a single-ward net), and the **Emergency Response Director (ERD)** or the specialist announces it on the net.

Above the stake: the Stake EOC reports to the **council line** (the Area Seventy) and the **welfare line** (the Welfare and Self-Reliance Manager, WSRM, then the Area Welfare and Self-Reliance Manager, AWSRM) by the same ladder: email, any internet or a landline, Winlink radio, then a satellite phone or the stake liaison at the county EOC.
Part of the stake cut off? A **Satellite EOC** in a ward building covers those wards and rolls up to the Stake EOC.

Turn over → Card 4, side 2: The Three Forms & What the Bishop Does

FOR BISHOPS, STAKE PRESIDENTS & EMERGENCY RESPONSE DIRECTORS

CARD 4 · BACK · SIDE 2 OF 2

The Three Forms & What the Bishop Does

THE THREE FORMS

Disaster Report

Documents a damaged home or injured member. Routes to the Stake EOC, then up the welfare line (WSRM, AWSRM).

Supply Order

Requests food, equipment, or supplies. Needs ERD and welfare line approval (WSRM, then AWSRM) before it is filled.

Work Crew Log

Records volunteer crew hours and tasks completed. Gives the Stake President accountability data for reporting.

WHAT THE BISHOP NEEDS TO DO

- ☐ Ensure at least one ward member is trained as Emergency Response Director
- ☐ Identify your EMCOMM HAM operator (may be a ward or stake calling)
- ☐ Put the forms' web address (URL) and QR (Quick Response) code in ward emergency preparedness materials
- ☐ Give the stake specialist your ward's FRS/GMRS channel, HAM operator and Satellite EOC building for the stake PACE sheet
- ☐ See that every volunteer keeps blank paper forms and a pen in the go-bag (portal → Paper forms)
- ☐ Take part in the yearly 2-hour practice drill (card 9 explains a drill)

> **You do not need to understand the technology.** The system is designed so that the Bishop gives direction and volunteers do the rest. The Stake EOC gives you accurate totals for your reports to the Stake President.

> **The Stake President decides:** the PACE level (on the specialist's recommendation); the SITREP (situation report) interval; opening a Satellite EOC; moving to the backup EOC; approving the stake PACE sheet; consent before a drill uses real contacts.

Forms align with the Church PDF (Portable Document Format) forms: PD60000184 Disaster Report • PD10052205 Supply Order • PD10052209 Work Crew Log

Church of Jesus Christ EMCOMM is an independent volunteer project created by Travis Hilton (W9TLH), not an official product of The Church of Jesus Christ of Latter-day Saints.

travislhilton.github.io/church-emcomm-wnlk-forms/forms/

DRILL CONTROLLER — WELFARE AND SELF-RELIANCE SPECIALIST (EMERGENCY COMMUNICATIONS) OR EMERGENCY RESPONSE DIRECTOR (ERD)

CARD 5 · FRONT · SIDE 1 OF 2

Running a Drill with the Church of Jesus Christ EMCOMM Simulator

Share this card

BEFORE THE ROOM FILLS

1. Start the EOC (Emergency Operations Center) server and set it up
   Setup tab: EOC level, name and roster (the playing wards). **Reset for the session** (step 4) opens the drill event. Wall display on the TV.
2. Start the simulator on the Windows EOC laptop
   Double-click **Church of Jesus Christ EMCOMM Simulator** on the Desktop (installer role 3), then open `http://<this laptop>:8090`. The organization pack and map data stay on this laptop.
3. Setup tab: pack → privacy → what this simulator plays → EOC → scenario → speed
   Pseudonymized (invented names) unless the Stake President agreed to real contacts. Add missing callings under the pack. Plays **this Stake EOC**, **a Satellite EOC** or **a Council / Area EOC**. Speed 2× for a two-hour room, 1× for four hours.
4. Session tab: rehearse, then **Reset for the session**
   Reset opens a fresh drill event; the EOC screens show *waiting for the trainer's GO*. Print the Roles tab.

DURING THE RUN

5. Hand each newcomer **card 9** (Your First Drill). Give the instructions, then **GO** on the Session tab. Hand out each card as it comes due
   Reports reach the EOC by the path the PACE (Primary, Alternate, Contingency, Emergency) level selects. Net cards to the HAM (amateur radio) operators, prompts to the role named, paper to a runner. After a restart: **Resume** on the Session tab.
6. PACE changes follow the scenario's triggers
   The specialist recommends, the Stake President decides, the ERD or the specialist announces it on the net; then you set the level on the Run tab and it reaches the EOC header. Never change it for them.
7. Watch the scoreboard; at the end open the after-action report
   Run tab: needs met, overdue, score. Needs tab: **Waive** what the room is not playing. Hot wash tab (the after-drill review): mark each line, then **After-action report**. Results on any device: `http://<laptop>:8090/results`.
8. **Debrief for the room**
   Session tab step 5 → projector slides (← → move, F full screen): what went well, the score, one thing per role, the date of the next drill. Pick the date before people leave.

> **Several EOC laptops: one simulator each,** same scenario and seed. Operators press **I am ready** on the drill bar (remote sites say so by voice). On every laptop's Session tab, step 3: enter the agreed time in **or start every laptop at**, then **Schedule**. The clocks start together.

Turn over → Card 5, side 2: What the Simulator Sends, Who Plays, What the Hot Wash Reads

DRILL CONTROLLER — WELFARE AND SELF-RELIANCE SPECIALIST (EMERGENCY COMMUNICATIONS) OR ERD

CARD 5 · BACK · SIDE 2 OF 2

What the Simulator Sends, Who Plays, What the Hot Wash Reads

INJECTS — WHAT YOU DO WITH EACH

Report — sent to the EOC by the level in force: **P / A** phone upload · **C** a Winlink `.mime` into the EOC's simulated Winlink inbox; the EOC files it by itself (a paper card if the EOC has no Winlink) · **E** paper card for a runner to carry

Note — lands in the EOC notes log prefixed SIM: (roads, weather, the county)

Net card — hand it to the ward's HAM to read on the stake net

Prompt — hand it to the role named: a recommendation, a decision, a SITREP (situation report) that is due

Work item — lands on the EOC's Work Items list (mission office, county, welfare line, Stake President); the EOC owns it, acts, records the decision

Consequence — fires when a need is met (the resolution) or overdue (the caller comes back). Reply — the welfare line closes an item set UP, DONE with the decision

> **Role players:** Stake President · Welfare and Self-Reliance Specialist · Emergency Response Director (ERD) · a bishop per playing ward · Team Leaders · ward HAM operators · Stake EOC operators · a Satellite EOC operator · the welfare line (the Welfare and Self-Reliance Managers) · the Area Seventy (email only) · a Council / Area EOC if the drill opens one · you, the controller.

The scoreboard reads the Work Items list: every need owned in time (HIGH within 10 minutes), closed or set UP in time, leadership questions answered as a recorded decision, paper and net reports typed in within 25 minutes with the numbers as on the card; SITREP #1 by the time the scenario sets; nothing HIGH left without an owner. Tell the EOC operators on day one: **own it, move it, write the decision in.**

> **Privacy:** pseudonymized runs still show real unit and building names. For an issue or screenshot, use the invented Juniper Plains Area or "Report as text, units redacted". A real-contacts run never leaves the room. The mode is stamped on every run and export.

> **Tabletop without the room:** one controller, one EOC operator, 10× speed, the invented Juniper Plains Area: forty minutes shows every path and the hot wash.

Church of Jesus Christ EMCOMM is an independent volunteer project created by Travis Hilton (W9TLH), not an official product of The Church of Jesus Christ of Latter-day Saints.

travislhilton.github.io/church-emcomm-wnlk-forms/forms/

CARD 6 · FRONT · SIDE 1 OF 2

Satellite EOC — Closer to the Damage, Reporting to the Stake Center

Share this card

WHEN AND WHERE

The stake specialist (Welfare and Self-Reliance Specialist, emergency communications) recommends, the **Stake President decides**: open one when a group of wards cannot reach the Stake Center in reasonable time (roads cut, the river between, the Stake Center damaged or dark). A ward building with power, a HAM (amateur radio) station and Wi-Fi.

It covers the wards or the part of the community the Stake President assigns to it. One stake can have several.

SETUP TAB, ONCE

Level **Satellite** · this EOC's name · the wards it covers · parent = the **Stake Center EOC** (name, drop email, Winlink address) · the SITREP (situation report) interval leadership set.

Comms sheet: your Winlink address and net frequency, so the stake sheet sends your wards to *you*.

WHAT COMES IN

Disaster Reports, Supply Orders and Work Crew Logs from your wards: phones on your Wi-Fi (the wall QR (Quick Response) code), Winlink auto-ingest, the Drop Folder (email, text, USB (Universal Serial Bus) drive).

Roster tab: which of your wards have reported, which are overdue, missionaries not accounted for.

WHAT GOES UP, WITH EVERY SITREP

The **SITREP** text to the Stake Center EOC (and anything the Stake President asked for by voice on the net).

Export Roll-up JSON (JavaScript Object Notation, a data file) to the Stake Center EOC by the path the PACE (Primary, Alternate, Contingency, Emergency) level allows (back of this card). The stake merges it; your wards then count in the stake's SITREP without re-keying.

Supply Orders are not approved here: they ride up in the roll-up and the welfare line answers through the Stake Center.

WORK ITEMS

Own what the satellite can do (a shelter check, a crew, a headcount). Anything for the Stake President or the welfare line: set it **Up**; it rides in the roll-up and arrives open at the Stake Center.

> **Card 3** is how to run the Message Center (start-up, auto-ingest, tabs, status, handoff). This card is what your level does and what it owes the level above.

Turn over → Card 6, side 2: The Chain, the Roll-up Path, Phones and Drills

SATELLITE EOC (EMERGENCY OPERATIONS CENTER) — CARD 6 OF THE EOC SET

CARD 6 · BACK · SIDE 2 OF 2

The Chain, the Roll-up Path, Phones and Drills

THE CHAIN AT A GLANCE

EOC	Reports from	SITREP to	Roll-up JSON to
Satellite ◀ you	its wards	Stake Center EOC	Stake Center EOC
Stake Center	wards + satellites	Stake President, council line, welfare line	Council / Area EOC, if open
Council / Area	stakes	Area Presidency / Church headquarters, as directed	—

SITREP = situation report. The council line is the Area Seventy; the welfare line is the Welfare and Self-Reliance Manager (WSRM), then the Area Welfare and Self-Reliance Manager (AWSRM). A Council / Area EOC exists only when the council or the welfare region opens one.

ROLL-UP: HOW THE FILE TRAVELS

Setup tab → **Export Roll-up JSON** (“only new since last roll-up” ticked) → send it with every SITREP.

P / A (cellular, any internet): attach it to an email to the parent EOC’s drop email. **C** (radio): attach it to a Winlink message to the parent’s Winlink address. First Winlink peer-to-peer (P2P) over VARA FM straight to a nearby parent station, then VARA FM through a gateway, then VARA HF (VARA: the sound-card radio modem Winlink uses). **E** (runner): on a USB drive with the printed SITREP.

At the parent nothing is clicked: the Drop Folder and Winlink watchers merge it within 10 seconds and log “Roll-up received from …”. From USB: drop it in the Drop Folder. Nothing is counted twice.

> **Any device in the room, no app needed:** scan the wall QR code (or open `http://<server-ip>:8080/m`): new reports, **Send to EOC**, the **Work items** list (tap an item: **Take it**, In work, Up, Done; your name goes in its log). **Paper by runner (Emergency):** type it in at `/forms/dr`, `/forms/so` or `/forms/wcl` and tap **Send**; keep blank paper forms on hand (add `?blank=1`, **Print**).

> **In a drill:** one simulator per EOC. The purple **drill bar** on every screen says what this EOC plays, the clock or the start time, and who is ready: press **I am ready**. Every simulated report says SIMULATED; real reports still go through. New to drills? Read **card 9**.

Church of Jesus Christ EMCOMM (emergency communications) is an independent volunteer project created by Travis Hilton (W9TLH), not an official product of The Church of Jesus Christ of Latter-day Saints.

CARD 7 · FRONT · SIDE 1 OF 2

Stake Center EOC — The Stake's Picture, Reporting to the Two Lines Above

Share this card

WHO DECIDES

The stake **Welfare and Self-Reliance Specialist (emergency communications)** recommends the PACE (Primary, Alternate, Contingency, Emergency) level and when to open a Satellite EOC; the **Stake President decides**; the ERD (Emergency Response Director) or the specialist announces it. Set the PACE level on the Setup tab the moment it changes and log the time.

SETUP TAB, ONCE

Level **Stake** · this EOC's name · parent = the two lines above the stake: the **council line** (Area Seventy; decisions) and the **welfare line** (the Welfare and Self-Reliance Manager, WSRM, then the Area Welfare and Self-Reliance Manager, AWSRM; supplies, approvals, reporting), or a **Council / Area EOC** when one is open · the SITREP (situation report) interval leadership set.

Comms sheet: every EOC's Winlink address, gateways in order, net frequencies; **Export sheet JSON** (JavaScript Object Notation, a data file) to every Satellite EOC.

WHAT COMES IN

Every ward not covered by a satellite (phones, Winlink, Drop Folder; USB (Universal Serial Bus) drives too) and each **Satellite EOC's roll-up** (merges itself; **Via** on the Messages tab shows which EOC it came through; nothing is counted twice).

Roster tab: wards and bishops, who has reported, who is overdue, missionaries not accounted for.

WHAT GOES UP, WITH EVERY SITREP

SITREP to the Stake President, the council line and the welfare line: first as soon as possible, then on the interval leadership set. PACE level in force in the header.

Supply Orders to the welfare line for approval; record the AWSRM's answer on the order. **Headquarters assistance** requests go up the same way.

Export Roll-up JSON only to a Council / Area EOC when one is open (back of this card). Otherwise the SITREP is the stake's report upward.

WORK ITEMS

The mission office, the county, the Stake President and the welfare line ask through this list; the reports add their own. Give every HIGH item an owner at once. **Up** = sent to the line above; write the **decision** when it comes back. The same list is on every phone in the room.

> **Card 3** is how to run the Message Center (start-up, auto-ingest, tabs, status, handoff). This card is what your level does and what it owes the level above.

Turn over → Card 7, side 2: The Chain, the Roll-up Path, Phones and Drills

CARD 7 · BACK · SIDE 2 OF 2

The Chain, the Roll-up Path, Phones and Drills

THE CHAIN AT A GLANCE

EOC	Reports from	SITREP to	Roll-up JSON to
Satellite	its wards	Stake Center EOC	Stake Center EOC
Stake Center ◀ you	wards + satellites	Stake President, council line, welfare line	Council / Area EOC, if open
Council / Area	stakes	Area Presidency / Church headquarters, as directed	—

SITREP = situation report. The council line is the Area Seventy; the welfare line is the Welfare and Self-Reliance Manager (WSRM), then the Area Welfare and Self-Reliance Manager (AWSRM). A Council / Area EOC exists only when the council or the welfare region opens one.

ROLL-UP: HOW THE FILE TRAVELS

Setup tab → **Export Roll-up JSON** ("only new since last roll-up" ticked) → send it with every SITREP.

P / A (cellular, any internet): attach it to an email to the parent EOC's drop email. **C** (radio): attach it to a Winlink message to the parent's Winlink address. First Winlink peer-to-peer (P2P) over VARA FM straight to a nearby parent station, then VARA FM through a gateway, then VARA HF (VARA: the sound-card radio modem Winlink uses). **E** (runner): on a USB drive with the printed SITREP.

At the parent nothing is clicked: the Drop Folder and Winlink watchers merge it within 10 seconds and log "Roll-up received from …". From USB: drop it in the Drop Folder. Nothing is counted twice.

> **Any device in the room, no app needed:** scan the wall QR (Quick Response) code (or open `http://<server-ip>:8080/m`): new reports, **Send to EOC**, the **Work items** list (tap an item: **Take it**, In work, Up, Done; your name goes in its log). **Paper by runner (Emergency):** type it in at `/forms/dr`, `/forms/so` or `/forms/wcl` and tap **Send**; keep blank paper forms on hand (add `?blank=1`, **Print**).

> **In a drill:** one simulator per EOC. The purple **drill bar** on every screen says what this EOC plays, the clock or the start time, and who is ready: press **I am ready**. Every simulated report says SIMULATED; real reports still go through. New to drills? Read **card 9**.

Church of Jesus Christ EMCOMM (emergency communications) is an independent volunteer project created by Travis Hilton (W9TLH), not an official product of The Church of Jesus Christ of Latter-day Saints.

CARD 8 · FRONT · SIDE 1 OF 2

Council / Area EOC — Only When the Council or the Welfare Region Opens One

Share this card

WHEN IT EXISTS

There is no standing Area EOC. The coordinating council (Area Seventy) or the welfare region opens one when several stakes are hit, usually at the station of the Area Welfare and Self-Reliance Specialist (often a HAM, amateur radio operator, who works both the council line and the welfare line).

Until then each Stake EOC reports straight to the two lines above it, and this card is not in use.

SETUP TAB, ONCE

Level **Council / Area** · this EOC's name · the stakes it covers (the Roster tab then lists stakes, not wards) · its drop email and Winlink address, given to every Stake EOC on the comms sheet.

WHAT COMES IN

Each Stake EOC's **SITREP** (situation report) and **roll-up** (a JSON, JavaScript Object Notation, data file). Roll-ups by email or Winlink file themselves; from a USB (Universal Serial Bus) drive, drop the file in the Drop Folder. **Via** shows the Stake EOC.

Roster tab: which stakes have reported, which are overdue; totals across stakes on the wall display.

WHAT IT DOES

Supply Order totals by stake for the Area Welfare and Self-Reliance Manager (AWSRM) and the storehouse (water, blankets, cleaning kits; which stake center receives); record the approval on each order.

Answering a Supply Order: open the item → **Reply to <stake EOC>** → send the .json to that stake's drop email or Winlink address; their item closes DONE with your decision.

Headquarters assistance requests from the stakes, consolidated. Its own SITREP (every stake's totals) to the Area Presidency and Church headquarters, as directed, on the interval they set.

WORK ITEMS

Stake items marked **Up** arrive here open, named with the stake; give each an owner. Items from the welfare line (totals by a deadline) land only on the Council / Area EOC's list, not the stakes'.

IN A DRILL

The Area simulator plays the councils. Stakes nobody plays arrive as roll-up files at the SITREP times. New to drills? Card 9.

> **Card 3** is how to run the Message Center (start-up, auto-ingest, tabs, status, handoff). This card is what your level does and what it owes the level above.

Turn over → Card 8, side 2: The Chain, the Roll-up Path, Phones and Drills

COUNCIL / AREA EOC (EMERGENCY OPERATIONS CENTER) — CARD 8 OF THE EOC SET

CARD 8 · BACK · SIDE 2 OF 2

The Chain, the Roll-up Path, Phones and Drills

THE CHAIN AT A GLANCE

EOC	Reports from	SITREP to	Roll-up JSON to
Satellite	its wards	Stake Center EOC	Stake Center EOC
Stake Center	wards + satellites	Stake President, council line, welfare line	Council / Area EOC, if open
Council / Area ◀ you	stakes	Area Presidency / Church headquarters, as directed	—

SITREP = situation report. The council line is the Area Seventy; the welfare line is the Welfare and Self-Reliance Manager (WSRM), then the Area Welfare and Self-Reliance Manager (AWSRM). A Council / Area EOC exists only when the council or the welfare region opens one.

ROLL-UP: HOW THE FILE TRAVELS

Setup tab → **Export Roll-up JSON** ("only new since last roll-up" ticked) → send it with every SITREP.

P / A (cellular, any internet): attach it to an email to the parent EOC's drop email. **C** (radio): attach it to a Winlink message to the parent's Winlink address. First Winlink peer-to-peer (P2P) over VARA FM straight to a nearby parent station, then VARA FM through a gateway, then VARA HF (VARA: the sound-card radio modem Winlink uses). **E** (runner): on a USB drive with the printed SITREP.

At the parent nothing is clicked: the Drop Folder and Winlink watchers merge it within 10 seconds and log "Roll-up received from …". From USB: drop it in the Drop Folder. Nothing is counted twice.

> **Any device in the room, no app needed:** scan the wall QR (Quick Response) code (or open `http://<server-ip>:8080/m`): new reports, **Send to EOC**, the **Work items** list (tap an item: **Take it**, In work, Up, Done; your name goes in its log). **Paper by runner (Emergency):** type it in at `/forms/dr`, `/forms/so` or `/forms/wcl` and tap **Send**; keep blank paper forms on hand (add `?blank=1`, **Print**).

> **In a drill:** one simulator per EOC. The purple **drill bar** on every screen says what this EOC plays, the clock or the start time, and who is ready: press **I am ready**. Every simulated report says SIMULATED; real reports still go through. New to drills? Read **card 9**.

Church of Jesus Christ EMCOMM (emergency communications) is an independent volunteer project created by Travis Hilton (W9TLH), not an official product of The Church of Jesus Christ of Latter-day Saints.

travislhilton.github.io/church-emcomm-wnlk-forms/forms/

EVERY DRILL PARTICIPANT — ANY ROLE

CARD 9 · FRONT · SIDE 1 OF 2

Your First Drill

Share this card

WHAT A DRILL IS

- A drill is practice. The events are invented.
- Every simulated report says **SIMULATED**.
- Anything you send: tick **THIS IS AN EXERCISE** at the top of the form.

> **Real emergencies always come first.** If a real one happens, say "**real world**". The drill stops.

WHAT HAPPENS IN THE ROOM

1. **The controller gives a short briefing.** Listen for your role and your EOC (Emergency Operations Center).
   EOC operators: press **I am ready** on the purple drill bar.
2. **The controller says GO.** The drill clock starts.
3. **Slips of paper arrive during the drill.** Do what each one says (table below).
4. **The controller says when the drill ends.** Stop, then join the debrief (side 2).

Net card	For a HAM (amateur radio) operator: read it aloud on the radio net.
Prompt card	A decision or a job for the role named on it.
Paper card	A report on paper. Carry it to the EOC; an operator types it in.

Other reports reach the EOC screens by themselves: from phones, by Winlink radio email, or as files.

> **What to bring:** a phone, tablet or laptop, charged (no app? scan the code on the EOC wall); a pen; the card for your role (side 2).

> **Not sure what to do?** Ask the controller. Write down what you did and the time. Do your best: mistakes are how a drill teaches.

Turn over → Card 9, side 2: Your Role, Five Words, After the Drill

EVERY DRILL PARTICIPANT — ANY ROLE

CARD 9 · BACK · SIDE 2 OF 2

Your Role, Five Words, After the Drill

YOUR ROLE AND YOUR CARD

Helping Hands volunteer	**Card 1.** Fill in forms on your phone and send them.
HAM operator	**Card 2.** Send forms by Winlink; talk on the net.
EOC operator	**Cards 3 and 6–8.** Log reports, own work items, write the SITREP (situation report).
Bishop or other leader	**Card 4.** Give direction and make decisions.
Team Leader or Crew Chief	**Card 10.** Lead a crew; get its reports to the EOC.
Drill controller	**Card 5.** Runs the simulator and the clock.

Playing a leader (Stake President, specialist, welfare line)? Answer each prompt card as that person would.

FIVE WORDS TO KNOW

EOC — Emergency Operations Center: the room with a laptop, a radio and Wi-Fi that collects every report.

PACE — the order of ways to send: **P** Primary, cell phone · **A** Alternate, any internet anywhere · **C** Contingency, radio (Winlink by VARA FM, then VARA HF: the radio modems Winlink uses) · **E** Emergency, a runner with paper.

SITREP — situation report: the EOC's summary for leaders. The first as soon as possible, then on the interval leaders set.

ERD — Emergency Response Director: leads the response. The stake specialist recommends the PACE level, the Stake President decides, the ERD or the specialist announces it.

HAM / Winlink — a HAM is a licensed amateur radio operator. Winlink is email by radio: it carries the forms when phones and internet are down.

After the drill: the debrief. What went well. One thing to do better. The date of the next drill.
Results on your device: the controller gives the address.

Feedback? Tell your Team Leader or the stake Welfare and Self-Reliance Specialist (emergency communications).

Church of Jesus Christ EMCOMM is an independent volunteer project created by Travis Hilton (W9TLH), not an official product of The Church of Jesus Christ of Latter-day Saints.

HELPING HANDS TEAM LEADER AND CREW CHIEF

CARD 10 · FRONT · SIDE 1 OF 2

Leading a Crew

Share this card

BEFORE YOU GO OUT

- ☐ Give a safety briefing. Check that everyone can do the work.
- ☐ Tell your ERD (Emergency Response Director) where the crew is going and when it will be back.
- ☐ Everyone has the app and the three forms on the phone (card 1).
- ☐ Everyone knows the order to send, the PACE plan: **P** Primary, cell · **A** Alternate, any internet · **C** Contingency, radio by a HAM (amateur radio) operator · **E** Emergency, paper by runner.
- ☐ Know your EOC (Emergency Operations Center): its address, email and Winlink address are on the stake Comms Sheet.

IN THE FIELD

1. **Check in every volunteer:** name, ward, start time.
2. **Volunteers fill** Disaster Reports (damage, injuries, needs) and Supply Orders (what is needed).
3. **The Crew Chief fills the Work Crew Log** at the end of the shift.
   Crew Chief section, then each Crew Member: Name, Ward, Hours Worked, Work Order Address. Tick the Safety Certification box only if every member had the safety orientation and is able to do the work.
4. **Collect the reports.** Get them to the EOC by the first PACE path that works.
5. **Paper only (E)?** Carry it to the EOC, or hand it to a runner or a HAM operator.

> **Safety.** Stop work if it is unsafe. No one works alone. Never enter a damaged building. Report every injury on a Disaster Report (Volunteer injuries or accidents).

Turn over → Card 10, side 2: Sharing the Forms, What the EOC Needs, End of Shift

HELPING HANDS TEAM LEADER AND CREW CHIEF

CARD 10 · BACK · SIDE 2 OF 2

Sharing the Forms, What the EOC Needs, End of Shift

SHARE THE FORMS WITH YOUR CREW

- ☐ Post the QR (Quick Response) code posters at staging areas and sign-in tables. Print them from `travislhilton.github.io/church-emcomm-wnlk-forms/forms/qr-posters.html`
- ☐ Or give out the portal address: `travislhilton.github.io/church-emcomm-wnlk-forms/forms/`
- ☐ In a drill, everyone ticks **THIS IS AN EXERCISE** (card 9 explains a drill).

WHAT THE EOC NEEDS FROM YOU, AND WHEN

First report as soon as possible: where you are, what you see, who is hurt.

Then reports on the schedule your ERD (Emergency Response Director) gives.

Supply Orders as soon as a need is known. The ERD and the welfare line approve them before they are filled.

A Work Crew Log at the end of every shift.

> **Who you report to:** your ERD, then the Stake EOC (or the Satellite EOC that covers your ward). Send forms to the EOC on the stake Comms Sheet.

END OF SHIFT

- ☐ Every volunteer checked out; hours written down.
- ☐ Work Crew Log filled in, Safety Certification box ticked, sent.
- ☐ Every phone's Outbox empty (nothing waiting), or the paper copies handed in.
- ☐ Injuries and unsafe places reported.
- ☐ Tell your ERD what is left to do tomorrow.

Something not working? Tell your ERD or the stake Welfare and Self-Reliance Specialist (emergency communications).

Church of Jesus Christ EMCOMM is an independent volunteer project created by Travis Hilton (W9TLH), not an official product of The Church of Jesus Christ of Latter-day Saints.